Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Cynet Connectors

This connector allows Stellar Cyber to ingest logs from Cynet and add the records to the data lake.

It also lets you lock down a device that is associated with an event reported by another connector. In Stellar Cyber, this connector is used to contain (isolate) or shut down the host, using Stellar Cyber actions.

If you use a Cynet connector to perform a Contain Host or Shutdown Host action on a host that is already disabled, shutdown, or otherwise not reachable, Cynet returns a status that the request was successful which is reported in the Stellar Cyber UI. If you are not certain whether an action was successful, you may verify it in the Cynet dashboard.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Cynet

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Alerts	Syslog	msg_class:
Audit Logs	Assets (for Hosts)	`cynet_alert`
Hosts		`cynet_audit_log`

Content Type	Index	Locating Records

		`cynet_host`
		
		msg_origin.source:
		`cynet`
		
		msg_origin.vendor:
		`cynet`
		
		msg_origin.category:
		`endpoint`

Domain

<Host URL>

where <Host URL> is a variable from the configuration of this connector

Response Actions

Action	Required Fields
Contain Host	Any value other than an IP Address in at least one of these fields: `hostip_host`, `srcip_host`, `computer_name`, or `host.name`
Shutdown Host	Any value other than an IP Address in at least one of these fields: `hostip_host`, `srcip_host`, `computer_name`, or `host.name`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Host URL, Username, Password, and Client ID

Adding a Cynet Connector

To add a Cynet connector in Stellar Cyber:

1. Obtain Cynet credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining Cynet Credentials

To configure your Cynet connector in Stellar Cyber, you will need the following information from your Cynet deployment:

- URL for the Cynet API access (https://pov.api.cynet.com/)
- Username

- Password


  The password sh not include non-ASCII special characters.

- Client ID for the tenant (site) you want to manage (for MSSP configurations, you can find the client id in Global Settings > Client Site Manager > Sites Status)


Adding the Connector in Stellar Cyber

With the configuration information handy, you can add the Cynet connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Cynet** from the **Type** dropdown.



   The asterisk (*) indicates a required field.


6. For **Function**, enable **Collect**. Or, if you want to contain hosts or shutdown hosts, enable **Respond**.
7. Enter a **Name**.

   Notes:

   - This field does not accept multibyte characters.

- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Enter the **Host URL**. This is the URL noted above for API access.

For release versions prior to v4.3.4, ensure the URL does not include a trailing "/" symbol.

13. Enter the **Username** you noted above.
14. Enter the **Password** you noted above.
15. Enter the **Client ID** you noted above.
16. Choose the **Interval (min)**. This is how often the logs are collected.
17. Choose the **Content Type** you would like to collect. The logs for **Hosts**, **Alerts**, and **Audit Logs** are supported.

The **Hosts** content type is always selected and cannot be removed from the configuration as it is required for host information.

18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.

The **Connector Overview** appears.


The new connector is immediately active. For the Respond function, you can now contain hosts from the event display, and view or edit those actions on the **Endpoint Actions** page.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:
   - For **Hosts**, **Alerts**, and **Audit Logs**, change the **Indices** to **Syslog**.
   - For **Hosts** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.