Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Fortigate Firewall Connectors

You can connect Stellar Cyber to firewalls so that you can quickly and easily implement firewall rules on those firewalls from within Stellar Cyber, while you are threat hunting. You can configure firewall actions or manually trigger a firewall action from the event display. For either action you must already have your firewall connected.

Connector Overview: Fortigate Firewall

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP** or **Sensor**
- Interval: **N/A**

Collected Data

N/A

Domain

https://<Device IP Address>:<Device Port>

where <Device IP Address> and <Device Port> are variables from the configuration of this connector

Response Actions

Action	Required Fields
Block IP	`srcip` or `dstip`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- For API Token Auth Method: API Token, Device IP Address, Source IP Group, Destination IP Group, and Virtual Domain Name
- For User Name / Password Auth Method: User Name, Password, Device IP Address, Source IP Group, Destination IP Group, and Virtual Domain Name

Adding a Fortigate Firewall Connector

To add a Fortigate firewall connector:


1. Create API user
2. Create firewall rules
3. Obtain an API Token
4. Add the connector in Stellar Cyber
5. Test the connector

Creating API User


To create an API user, first create an Admin Profile, then create the API user either for a single VDOM or multiple VDOMs.

Creating Admin Profile

1. Navigate to **Admin Profiles** under **System**.
2. Click **Create New**.



3. For the Access Permissions, next to **Firewall**, click **Custom**.
4. For the Firewall **Address**, click **Read/Write**.




5. Click **OK**.


Creating an API User for a Single VDOM

To create an API user for a single VDOM:

1. Navigate to **Administrators** under **System**.
2. Click **Create New** and select **Administrators**.



3. In the New Administrator window, enter a **Username**, **Password**, and **Confirm Password**.




4. For the **Administrator Profile**, select the profile you previously created.
5. Click **OK**.

Creating an API User for Multiple VDOMs

To create an API user for multiple VDOMs, follow the initial steps in [Creating an API User for a Single VDOM]:

1. In the New Administrator window, in addition to selecting the **Administrator Profile** you previously created, also select **Virtual Domains**.



2. Click **OK**.

Creating Firewall Rules

To trigger firewall actions, you must have rules on your Fortigate firewall that you can trigger. Create the rules with a user that has access rights to modify rules.


Login to Fortigate with a user that you have previously logged in with. Or, if you have created a new user, log in to Fortigate as that user and accept the license agreement before starting this procedure.

To create the firewall rules:


1. Create two address groups. You will use these when adding the connector in Stellar Cyber. When a firewall action is triggered, Stellar Cyber adds the IP address to one of these groups.

Do not use non-ASCII characters in IP address names. When blocking an IP address, there can be an existing address in the IP address group in which the IP address name has non-ASCII characters in it.


The following is an example of the source address group named **Stellar-Src-Group**:



The following is an example of the destination address group named **Stellar-Dst-Group**:




2. Click **OK** to save each address group.
3. Create two deny policies. The first policy is an example of an Inbound Deny rule named **Stellar_Inbound** with the following settings:
    - Incoming Interface: Internet (wan1)
    - Outgoing Interface: internal
    - Source = Stellar-Src-Group
    - Destination = all
    - Action = DENY



When there is a Block IP action from an alert and the direction is inbound, the IP address will be added in the Source address group to the firewall (Stellar-Src-Group in this example).

4. The second policy is an example of an Outbound Deny rule named **Stellar_Outbound** with the following settings:
    - Incoming Interface: internal
    - Outgoing Interface: Internet (wan1)
    - Source = all
    - Destination = Stellar-Dst-Group
    - Action = DENY



When there is a Block IP action from an alert and the direction is outbound, the IP address will be added in the Destination address group to the firewall (Stellar-Dst-Group in this example).

5. Click **OK** to save each rule.

Obtaining an API Token


There are two ways to authenticate with the Stellar Cyber connector: **API Token** or **User Name / Password**. The **API Token** Auth Method is recommended.

You generate an API token when you create a REST API administrator in the GUI or the CLI. Refer to the *FortiOS Administration Guide* for REST API administrator.


Adding the Connector in Stellar Cyber

To add a new Fortigate firewall connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Firewall** from the **Category** dropdown.
5. Choose **Fortigate** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

11. Choose the **Auth Method** to use **API Token** or **User Name / Password**.

    The **API Token** Auth Method is recommended.

    For **API Token** Auth Method, enter the **API Token** you noted above in Obtaining an API Token.

    For **User Name / Password** Auth Method:



The asterisk (*) indicates a required field.

    a. Enter the **User Name** to log in to the firewall. This user must have access rights to modify a rule.


    b. Enter the **Password** to log in to the firewall.

The password should not include non-ASCII special characters.

12. Enter the **Device IP Address**. This is the management IP address for the firewall.
13. (Optional) Enter the **Device Port**. The default is **443**.
14. Enter the **Source IP Group** to which to add the IP address. This is the source address group you created above in Creating Firewall Rules.
15. Enter the **Destination IP Group** to which to add the IP address. This is the destination address group you created above in Creating Firewall Rules.
16. Enter the **Virtual Domain Name**. This is where the rules were created.

    Virtual Domains (VDOMs) are used to divide a Fortigate into two or more virtual units that function independently. By default, the management VDOM is root.

17. Click **Next**. The final confirmation tab appears.



18. Click **Submit**.


The new firewall connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

> The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits,

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
			user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

© 2026 Stellar Cyber . All rights reserved.