Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Huntress Connectors

This connector allows Stellar Cyber to ingest logs from Huntress and add the records to the data lake. This connector integrates with the Huntress API to query for agents and incident reports.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Huntress

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Agents
Incident Reports
	Syslog
	Assets (for Agents)
		msg_class:
		`huntress_agent`
		`huntress_incident_report`
		
		msg_origin.source:
		`huntress`
		
		msg_origin.vendor:
		`huntress`
		
		msg_origin.category:

Content Type	Index	Locating Records
		`endpoint` (Agents) `mdr` (Incident Reports)

Domain

<Host URL>

where <Host URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

This connector ingests logs from Huntress to get the raw alerts that are stored in the Syslog index. Select the Incident Reports content type.

Stellar Cyber maps Huntress incidents. The incidents are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid`, `huntress_id`, `huntress.organization_id`, and `huntress.account_id`.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- Host URL, API Key, API Secret Key, and Organization ID

Locating Records

To search the alerts in the Alerts index or to search the Original Records in the Syslog index, use the query: `msg_class: huntress_incident_report`.

Adding a Huntress Connector

To add a Huntress connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion


Obtaining Huntress Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Huntress credentials:

- Host URL—hostname of the Huntress server. The default is: https://api.huntress.io/v1.
- API Key—API key associated with a user account, generated from Huntress, and used to authenticate with Huntress
- API Secret Key—API secret key associated with a user account, displayed when the API key is created, and used to authenticate with Huntress
- Organization ID—identifier of the organization

To generate an API key, refer to the Huntress documentation:

1. Log in as an administrative user to <your_account_subdomain>.huntress.io>.
2. Navigate to **API Credentials**.




3. Click the green **Generate** button.
4. Click **Confirm**, which generates a public and private key pair. This is your API key and API secret key.

> Store the API key and API secret key in a safe location. It cannot be retrieved later although it can be regenerated.


Locating the Organization ID

To locate the organization ID:

1. Navigate to **Organizations**.




2. Select the organization's name. The organization ID is located in the URL.




Adding the Connector in Stellar Cyber

To add a Huntress connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Huntress** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Enter the **Host URL** you noted above in Configuring Huntress Credentials.
13. Enter the **API Key** you noted above.
14. Enter the **API Secret Key** you noted above.
15. Enter the **Organization ID** you noted above.
16. Choose the **Interval (min)**. This is how often the logs are collected.

    The logs for **Agents** are queried every 24 hours.

17. Choose the **Content Type** you would like to collect. The logs for **Agents** and **Incident Reports** are supported.

    The **Agents** content type is always selected and cannot be removed from the configuration as it is required for host information.

18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.

The new connector is immediately active.

Partial and Complete Parsing

Parsing methods are as follows:

- Partial parsing—only essential header information is parsed, including the incident report URL, host URL, organization, and security product
- Complete parsing—in addition to the above, all processes, files, users, and threat information contained in the **body** field are parsed

The information in this section relates to the data enrichment done by the connector where the string under the **body** field is used to populate fields required for Machine Learning (ML) purposes. But if the size of the **body** is too large, complete parsing may not be done.

The following threshold levels, T1 and T2, manage data flow and system performance as follows:

- Threshold T1 (500KB)— set to prevent sending large data files through the Stellar Cyber data platform
- Threshold T2 (5MB)—aims to avoid performance and memory issues

The handling of data sizes in relation to these thresholds is as follows:


- For data size S < T1—the **body** field is retained and complete data parsing is performed
- For T1 ≤ S < T2—data is fully parsed, but the **body** field is dropped to reduce size
- For S ≥ T2—only partial parsing is conducted and the **body** field is dropped

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - For **Agents** and **Incident Reports**, change the **Indices** to **Syslog**.

- For **Agents** only, change the **Indices** to **Assets**.

The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.