Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Managing Certificates

Learn more at Stellar Cyber Academy.

The following link takes you to a course on the Stellar Cyber Academy technical training portal where you can learn more about this topic by watching the suggested lesson.

M02 Administration Essentials for Tenants, Users, and System (03h:46m)

Certificate Management for the Stellar Cyber Platform (22m:00s)

Discover how to manage TLS certificates for on-premises or private cloud deployments. Learn to generate and configure certificates, ensuring secure connections to the Stellar Cyber Platform.

The first time you access a link on the portal during a session, you must log in to access content.

The **System | Saved Objects | Certificates** page provides a centralized location to manage both server and CA certificates. From here, you can view, edit, or delete existing certificates and upload new certificates. You can also see where an existing certificate is currently in use in Stellar Cyber.

Your user profile must have **Certificates** privilege enabled in **System | ORGANIZATION MANAGEMENT | Role-Based Access Control** to use this feature. Only the **Super Admin** and **Platform Admin** profiles have this privilege enabled by default.

The certificates you upload in the Certificates page can be applied to different Stellar Cyber components elsewhere in the user interface:

- **Server certificates** are used to validate communications between clients and different Stellar Cyber components (user interface, receivers, upgrades, and the CM service; you can apply different certificates to each). Once you've uploaded a server certificate, you can apply it to the DP in **System | ORGANIZATION MANAGEMENT | Settings**. You can upload multiple server certificates; however, only one can be in use at any time.

Refer to **Generating Server Certificates** for instructions on how to generate a Certificate Signing Request file and use it to obtain a certificate from your service provider.


- **CA certificates** are used to enable upgrades of Stellar Cyber sensors behind firewalls that use SSL inspection. Start by uploading the CA certificate(s) used for SSL inspection by a Tenant's firewall in **System | Saved Objects | Certificates**. Then:
    - Add the certificate to the DP's certificate repository in the **System | ORGANIZATION MANAGEMENT | Settings** page. Make sure you select the correct tenant when uploading the certificate.
    - Add the certificate to the Tenant's sensors in **System | DATA SOURCE MANAGEMENT | Sensors | Sensors**.

      Note that it is possible that the DP may be behind a different firewall than a sensor. Make sure you assign the CA certificate from the correct firewall to the corresponding Stellar Cyber component.

Stellar Cyber can parse chained certificates correctly.

Understanding the Certificates Page

The **Certificates** page lists each of the Server and CA certificates you've uploaded to the system. You can click the **Upload** button to open a dialog box where you can upload a new certificate to the system.




Each certificate you've uploaded to the system is listed with the following information:

- **Name** – The name you specified for the certificate when you uploaded it.
- **Tenant** – The tenant to which the certificate is assigned:

  CA Certificates – CA certificates must be associated with a specific tenant. In a multi-tenant environment, you can upload the CA certificates used for SSL inspection by different tenants' firewalls and assign them correspondingly in Stellar Cyber, enabling software upgrades for components behind firewalls that use SSL inspection.

  Server Certificates – Server certificates are used to secure communications with different Stellar Cyber components and are not associated with a specific tenant. This field always shows **All Tenants** for Server certificates.
- **Issuer** – The issuing authority for the certificate, as read from the certificate itself.
- **Type** – Either CA or Server, depending on what you selected during the upload process.
- **Expiration Date** – The date the certificate expires, as read from the certificate itself.

- **Domain** – The domain(s) for which the certificate is valid, as read from the certificate itself.
- **In Use** – Shows the number of place in Stellar Cyber in which the certificate is in use. You can hover your cursor over this entry to see a popup listing the places in Stellar Cyberwhere the certificate is in use, as illustrated below:



- Action Buttons:
  - Click  to edit a certificate.
  - Click  to delete a certificate.

See the Tables page for more information on working with Tables, including the common **Search, Export as CSV**, **Change Columns**, and **Refresh** tools.

Uploading Certificates

Use the following procedure to upload a new certificate to Stellar Cyber:

1. Navigate to **System | Saved Objects | Certificates** and click the **Upload**button.
2. Supply a **Name** for the certificate.

   The name you supply here is only used within Stellar Cyber to identify the certificate.
3. Select whether you are uploading a CA Certificate or a Server Certificate:

   If you are uploading a CA Certificate:

   a. Use the **Choose File** button in the **Certificate** field to browse to the location of the certificate you want to upload. The file you select must be a valid certificate in one of the following formats – .crt, .pem, .cer, .key, .p7b, .p7c, .der, or .p12.

   b. Use the **Tenant** dropdown to select the tenant associated with this certificate.

   Select the specific tenant whose certificate you are uploading. The certificate should be the one used to perform SSL inspection on the tenant's firewall where the sensor is located. With this certificate added to Stellar Cyber and assigned in the Sensors and Settings pages, Stellar Cyber software upgrades can work successfully in an environment where the firewall performs SSL inspection.

   If you are uploading a Server Certificate:

   a. Use the **Choose File** button in the **Certificate** field to browse to the location of the certificate you want to upload.

b. Use the **Choose File** button in the **Private Key** field to browse to the location of the private key associated with the selected certificate. You created the private key when you generated the Certificate Signing Request to send to your service provider in **Generating Server Certificates**.

Both the certificate and the private key you select must be in one of the following formats – .crt, .pem, .cer, .key, .p7b, .p7c, .der, or .p12.

4. Select **Submit** to upload the certificate to Stellar Cyber.

Stellar Cyber performs basic validation of the uploaded certificate to verify that it is a certificate. If you uploaded a Server certificate, Stellar Cyber verifies that the certificate and private key match. Once the key passes validation, Stellar Cyber adds it to the list in the **Certificates** page.

Next Steps

Once you've uploaded a certificate in the **Certificates** page, the next step is to apply it:

- **Server certificates** are applied to the DP in **System | ORGANIZATION MANAGEMENT | Settings**.
- **CA certificates** are applied as follows:
  - Add the certificate to the DP's certificate repository in the **System | ORGANIZATION MANAGEMENT | Settings** page.
  - Add the certificate to the Tenant's sensors in **System | DATA SOURCE MANAGEMENT | Sensors | Sensors**.

    The tenant specified during the upload of the CA certificate must match the tenant whose sensors you want to assign it to in the Sensors page.


You must have root scope to access the **System | ORGANIZATION MANAGEMENT | Settings** page. If the page doesn't appear in your user interface, you likely do not have the necessary RBAC settings to see it. Work with your platform administrator to apply the certificate.

Editing Certificates

You can edit a certificate in the **System | Saved Objects | Certificates** page by selecting the  button at the far right of its entry in the table. In response, the **Edit Certificate** window appears, allowing you to change the certificate's name, type, file, tenant assignment (CA certificates), or private key (server certificates).

Note that editing a certificate that is in use by the DP may result in a few minutes of system downtime while the changes are applied.


In addition, the **Edit Certificate** window provides high-level configuration information for the existing certificate, read from the certificate itself, as illustrated below:



Deleting Certificates

You can delete a certificate in **System | Saved Objects | Certificates** by clicking the button at the far right of its entry in the table.

Note that you can only delete a certificate that is not in use. Refer to the **In Use** column and use the popup there to determine where a certificate is in use, as illustrated below. Once you've removed the certificate from use, you can delete it.



© 2026 Stellar Cyber . All rights reserved.