Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Nessus Connectors

Learn more at Stellar Cyber Academy.

The following link takes you to a course on the Stellar Cyber Academy technical training portal where you can learn more about this topic by watching the suggested lessons.

M03 Modular Sensor Concepts and Configuration (08h:56m)

Modular Sensor Tenable Nessus Scanner (30m:00s)

Explore how the Stellar Cyber Modular Sensor includes a built-in Tenable Nessus vulnerability scanner. Learn how integrated vulnerability scanning simplifies deployment and enables efficient collection of vulnerability data for enhanced security monitoring and analysis.

Modular Sensor Platform Connector with Tenable (50m:00s)

Explore how to configure the Stellar Cyber Platform connector for Tenable.io. Learn to integrate Tenable.io with the Stellar Cyber Platform to automate collection of vulnerability scan and asset data for enhanced threat analysis and reporting.

The first time you access a link on the portal during a session, you must log in to access content.

Vulnerability scanners examine hosts for known and possible security vulnerabilities.

Nessus integration with Stellar Cyber enables organizations to conduct vulnerability scans and identify security risks across their network, providing real-time threat intelligence and automated response workflows to improve incident response and threat mitigation.

You can connect Stellar Cyber to your existing vulnerability scanner and have Stellar Cyber generate reports on the target hosts scanned.

See Tenable for information on configuring a Nessus scanner.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Nessus

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **Sensor**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
N/A	Scans Assets (host data if mac_address and ip_address)	msg_class: `security_scan` msg_origin.source: `nessus_scanner` msg_origin.vendor `tenable` msg_origin.category: `security_scan`

Domain

N/A

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Hostname, Port, Username, and Password (of the scanner)

Adding a Nessus Connector


To add a Nessus scanner:

1. Add the connector in Stellar Cyber
2. Test the connector
3. Verify ingestion


Adding the Connector in Stellar Cyber

To add a new Nessus vulnerability scanner connector in Stellar Cyber:

1. Log in to Stellar Cyber
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Vulnerability Scanner** from the **Category** dropdown.
5. Choose **Nessus Scanner** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Enter the **Hostname**. This is the FQDN or IP address of the scanner.

    Do not include https in the **Hostname**.

13. Enter the **Port**. The default is **8834**.
14. Enter the **Username** to log in to the scanner.
15. Enter the **Password** to log in to the scanner.

    The password should not include non-ASCII special characters.

16. Choose the **Interval (min)**. This is the time between polls of the scanner.
17. Click **Next**. The final confirmation tab appears.



18. Click **Submit**.


The new connector is immediately active and collects logs for the previous 30 days.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.

3. Click **Test** at the right side of that row. The test runs immediately.

Note that you ma[illegible]n only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota	The server or user license/quota will eventually recover. The connector will periodically retry the

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
		is exceeded.	query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - Change the **Indices** to **Scans**. Allow time for the vulnerability scan to complete.

     Data for this connector is not entered into the Scan Index until the scan is in a "Completed" status.

   - For host data, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.