Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Okta Connectors

Connectors allow Stellar Cyber to collect data from external sources and add it to the data lake. This topic describes the Okta connector, which connects to Okta's Identity Management service. For more information see the Okta web page.

The Okta connector allows you to collect logs and user information.

There can be any number of connectors installed in a system. Typically each tenant that uses Okta has their own connector.

Use an administrator role that has permissions for creating user tokens, viewing users, and viewing system event logs, for example at a minimum, the Read-Only Admin role.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Okta

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Syslog	Syslog	msg_class:
Users	Users	`okta`
		msg_origin.source:

Content Type	Index	Locating Records

		`okta`
		
		msg_origin.vendor:
		`okta`
		
		msg_origin.category:
		`iam`

Domain

https://<Hostname>

where <Hostname> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Hostname and API Token

Adding an Okta Connector

To add an Okta connector:

1. Create the Okta API token to use in Stellar Cyber
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion


Creating the Okta API Token

To create the Okta API token you'll use to configure the connector:


1. Log in to Okta.
2. Click **API**.




The **API** page appears.



3. Click **Create Token**. The **Create Token** screen appears.
4. Enter the name.



5. Click **Create Token**. The **Token Value** appears.




6. Copy the **Token Value**. You will enter this as the **API Token** in Stellar Cyber.
7. Click **OK, got it**. The **API** page appears, with your new token listed.


Adding the Connector in Stellar Cyber

To add an Okta connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **IdP** from the **Category** dropdown.
5. Choose **OKTA** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Enter the **Hostname** of the Okta service.

Do not include https in the Hostname.

13. Enter the **API Token**. This is the API **Token Value** you copied from Okta.
14. Choose the **Interval (min)**. This is how often the logs are collected.
15. Choose the **Content Type** you would like to collect. The logs for **Syslog** and **Users** are supported.
16. Click **Next**. The final confirmation tab appears.



17. Click **Submit**.

The new connector is immediately active.


Testing the Connector

If you've just added this connector, wait 5–10 minutes before testing.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !

Failure with summary of issue:





Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog** to check log ingestion or **Users** to check user data ingestion.

   The table immediately updates to show ingested Interflow records.



© 2026 Stellar Cyber . All rights reserved.