Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Palo Alto Networks CORTEX XDR Connectors 6.1.0

This connector allows Stellar Cyber to ingest logs from Palo Alto Networks CORTEX XDR and add the records to the data lake and, optionally, to issue the Isolate Endpoint response action.

The Palo Alto Networks CORTEX XDR connector integrates with the Palo Alto Networks CORTEX XDR API to process XDR information and query for several content types.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Palo Alto Networks CORTEX XDR

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **Yes** 6.1.0
- Runs on: **DP**
- Interval: **N/A**

Collected Data

Content Type	Index	Locating Records

Alerts
Audit Agent Report Logs
Audit Management Logs
Endpoints
Incidents
Risky Hosts
Risky Users
	Syslog
	Assets (for Endpoints)
		msg_class:
		`palo_alto_networks_cortex_xdr_alerts`
		`palo_alto_networks_cortex_xdr_events`
		`palo_alto_networks_cortex_xdr_audit_agent_report_logs`

Content Type	Index	Locating Records

Users 		`palo_alto_networks_cortex_xdr_audit_management_logs`
		`palo_alto_networks_cortex_xdr_endpoints`
		`palo_alto_networks_cortex_xdr_incidents`
		`palo_alto_networks_cortex_xdr_risky_hosts`
		`palo_alto_networks_cortex_xdr_risky_users`
		`palo_alto_networks_cortex_xdr_users`
		
		msg_origin.source:
		`palo_alto_networks_cortex_xdr`
		
		msg_origin.vendor:
		`palo_alto_networks`
		
		msg_origin.category:
		`endpoint`



The Alerts Content Type can result in more than one msg_class as follows:

- one `palo_alto_networks_cortex_xdr_alerts`
- multiple `palo_alto_networks_cortex_xdr_events`

You cannot select `palo_alto_networks_cortex_xdr_events` as a Content Type.

Domain

<FQDN>

where <FQDN> is a variable from the configuration of this connector

Response Actions

Action	Required Fields
Isolate Endpoint (Use the **Revert** button in **Automation | Action History** under the **Endpoint Actions** tab to unisolate the endpoint.)	`endpoint_id`

Third Party Native Alert Integration Details 6.1.0

This connector ingests logs from Palo Alto Networks CORTEX XDR to get the raw alerts that are stored in the Syslog index. Select the Alerts content type.

Stellar Cyber maps Palo Alto Networks CORTEX XDR alerts. The alerts are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid` and `palo_alto_networks.alert_id`.

There are the following categories of alerts:

- PAN NGFW
- XDR Agent
- XDR Analytics BIOC*
- XDR BIOC*
- XDR IOC

* Behavioral Indicator of Compromise (BIOC)

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- API Key ID, API Key, and FQDN

Locating Records 6.1.0

To search the alerts in the Alerts index or the Original Records in the Syslog index, use the query: `msg_class: palo_alto_networks_cortex_xdr AND _exists_: event.threat.name`

Adding a CORTEX XDR Connector

To add a Palo Alto Networks CORTEX XDR connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining CORTEX XDR Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Palo Alto Networks CORTEX XDR credentials:


- API Key ID
- API Key

  The API Key has an optional expiration time that can be set by the user.
- FQDN


Follow the guidance in Cortex XDR documentation for Get Started with Cortex XDR APIs.

To generate the API Key:

1. Log in as an administrative user to the CORTEX XDR portal.
2. Navigate to **Settings | Configurations**.




3. In **Configurations**, select **API Keys** under **Integrations**.




4. In the top-right corner, click **New Key**.
5. In the **Generate API Key** page, select either **Standard** or **Advanced** for the **Security Level** of the API key, then select the **Role** that gives you the appropriate access level for this key.

   Ensure that the role associated with the account has permission for the content type.

   For **Standard**:




   For **Advanced**:



   To integrate with CORTEX XSOAR, you must generate an **Advanced** key.


6. Click **Generate**.
7. Copy the API key, which you will need when configuring the connector in Stellar Cyber.

   Store the API key in a safe location. It cannot be retrieved later although it can be regenerated.



8. Click **Close**.
9. In the **API Keys** page, locate the API key in the table and note the API key ID, which you will need when configuring the connector in Stellar Cyber.
10. In the **API Keys** page, select the API key in the table and click **Copy API URL**. This is the FQDN, which you will need when configuring the connector in Stellar Cyber.

When you copy the API URL, it has the format: https://api-{fqdn}, however when you enter the FQDN in the next section, do not include the https://api- prefix, but enter the {fqdn} only.




You can test authentication by referring to Get Started with Cortex XDR APIs. With Advanced API keys, use the provided Python 3 example. With Standard API keys, use either the cURL example or the Python 3 example.


Adding the Connector in Stellar Cyber

To add a Palo Alto Networks CORTEX XDR connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System** | **INTEGRATIONS** | **Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Palo Alto Networks CORTEX XDR** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. Choose the **Function**: **Collect** to collect logs; **Respond** to isolate endpoints, or both functions.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the **API Key ID** you noted above in Obtaining CORTEX XDR Credentials.
13. Enter the **API Key** you noted above.

14. Enter the **FQDN** you noted above.

    When you copy the API URL in Obtaining CORTEX XDR Credentials, it has the format: https://api-{fqdn}, however when you enter the FQDN here, do not include the https://api- prefix, but enter the {fqdn} only.

15. Choose the **Content Type** you would like to collect. The logs for **Endpoints**, **Alerts**, **Audit Agent Report Logs**, **Audit Management Logs**, **Incidents**, **Risky Hosts**, **Risky Users**, and **Users** are supported.


    The **Endpoints** content type is always selected and cannot be removed from the configuration as it is required for host information.

    The logs for **Endpoints**, **Risky Hosts**, **Risky Users**, and **Users** are queried every 24 hours.

    The content types require different licenses as follows:

Content Type	Required License
Alerts	Cortex XDR Prevent, Cortex XDR Pro per Endpoint, or Cortex XDR Pro per GB
Audit Agent Report Logs	Cortex XDR Prevent, Cortex XDR Pro per Endpoint, or Cortex XDR Pro per GB
Audit Management Logs	
Endpoints	Cortex XDR Prevent or Cortex XDR Pro per Endpoint
Incidents	Cortex XDR Prevent, Cortex XDR Pro per Endpoint, or Cortex XDR Pro per GB
Risky Hosts	Identity Threat Module
Risky Users	Identity Threat Module
Users	Cortex XDR Pro per Endpoint, Cortex XDR Pro, or Cortex XDR Pro per GB

16. Click **Next**. The final confirmation tab appears.



17. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:
   - For all content types, change the **Indices** to **Syslog**.
   - For **Endpoints** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.