Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Palo Alto Networks Panorama Connectors

This topic covers a feature that is not available for all customers yet. See Early Access Program Features and Topics Under Development.

You can integrate Stellar Cyber with Palo Alto Networks Panorama to manage all your firewalls. While the Palo Alto Networks Firewall connector communicates with each individual firewall, the Palo Alto Networks Panorama connector provides centralized management capabilities over several Panorama firewalls.

You can configure firewall actions or manually trigger a firewall action from the event display.

Connector Overview: Palo Alto Networks Panorama

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP** or **Sensor**
- Interval: **N/A**

Collected Data

N/A

Domain

https://<Device IP Address>:<Device Port>

where <Device IP Address> and <Device Port> are variables from the configuration of this connector

Response Actions

Action	Required Fields
Block IP/Unblock IP	`srcip` or `dstip`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- User Name, Password, Device IP Address, Software Version, Device Group, Source IP Group, and Destination IP Group

Adding a Palo Alto Networks Panorama Connector


To add a new Palo Alto Networks Panorama connector:

1. Add a user
2. Add templates
3. Add device groups
4. Add address groups
5. Add policies
6. Add the connector in Stellar Cyber
7. Test the connector


Adding a User

To create an admin level user:

1. Under **Panorama**, select **Administrators**.



2. Click **Add**.



3. In the **Administrator** screen, enter the **Name** of the user. In this example, it is api-user.
4. Enter the **Password** and **Confirm Password**.
5. Select the following:
    a. **Administrator Type**: Dynamic
    b. **Admin Role**: Panorama administrator


c. **Password Profile**: None

6. Click **OK**.


Adding Templates

To add templates:


1. Under **Panorama**, select **Templates**.




2. Click **Add**.



3. In the **Template** screen, enter the **Name** of the template. In this example, it is Stellar_template.
4. Select a **Default VSYS**.
5. Click **OK**.
6. Next under **Templates**, click **Add Stack**.



7. In the **Template Stack** screen, enter the **Name** of the template stack. In this example, it is Stellar_Stack.




8. Add the Palo Alto firewall. In this example, it is PA-VM.
9. Add the template. In this example, it is Stellar_template.

10. Click **OK**.


Adding Device Groups

To add device groups:

1. Under **Panorama**, select **Device Groups**.



2. Click **Add**.




3. In the **Device Group** screen, enter the **Name** of the device group. In this example, it is Stellar_Device_Group.
4. Check the Palo Alto firewall. In this example, the PA-VM firewall was added to Stellar_Device_Group.
5. Add the template stack. In this example, it is Stellar_Stack.
6. Click **OK**.


Adding Address Groups

To add address groups:

1. Under **Objects**, select **Address Groups**.




2. Click **Add**.
3. In the **Address Group** screen, enter the **Name** of the source address group. In this example, it is Stellar_Src.




Do not select **Shared**.

4. Select a **Type**, for example, Static.
5. Select an IP address.
6. Click **OK**.
7. In the **Address Group** screen, enter the **Name** of the destination address group. In this example, it is Stellar_Dst.



Do not select **Shared**.


8. Select a **Type**, for example, Static.
9. Select an IP address.
10. Click **OK**.
11. View the address groups under the **Device Group** as follows:



Adding Policies

To add policies:


1. Under **Panorama**, select **Policies** > **Security** > **Pre Rules**.




2. Check that you have your **Device Group** selected. In this example, it is Stellar_Device_Group. Click **Add**.

   You will be adding two policies to refer to the source and destination address groups. In this example, they are Stellar_Src and Stellar_Dst.


   First, configure Stellar_Src.




3. In the **Security Policy Rule** screen, under the **General** tab, enter the **Name** of the policy. In this example, it is Stellar_Security_Policy_Deny_Src_Group.
4. Under the **Source** tab, select **Any** and then add the source address group. In this example, it is Stellar_Src.




5. Under the **Destination** tab, select **Any**.




6. Under the **Application** tab, select **Any**.




7. Under the **Service/URL Category** tab, select **Any**.




8. Under the **Actions** tab:
    a. For the **Actio** elect **Deny**.
    b. For the **Log Setting**, select **Log at Session End**.




9. Under the **Target** tab, for the Device Group, select the firewall. In this example, the Device Group is Stellar_Device_Group and the firewall is PA-VM.




10. Under the **Usage** tab, view the information.




11. Click **OK**.
12. Next, configure the policy to refer to the destination address group. In this example, it is Stellar_Dst.
13. In the **Security Policy Rule** screen, under the **General** tab, enter the **Name** of the policy. In this example, it is Stellar_Security_Policy_Deny_Dst_Group.




14. Under the **Source** tab, select **Any** and then select **Any**.




15. Under the **Destination** tab, add the destination address group. In this example, it is Stellar_Dst.



16. Under the **Application** tab, select **Any**.




17. Under the **Service/URL Category** tab, select **Any**.




18. Under the **Actions** tab:

    a. For the **Action**, select **Deny**.


    b. For the **Log Setting**, select **Log at Session End**.



19. Under the **Target** tab, for the Device Group, select the firewall. In this example, the Device Group is Stellar_Device_Group and the firewall is PA-VM.



20. Under the **Usage** tab, view the information.




21. Click **OK**.


Adding the Connector in Stellar Cyber

With the firewall rules in place, you can add the Palo Alto Networks Panorama connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Firewall** from the **Category** dropdown.
5. Choose **Palo Alto Networks Panorama** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


11. Enter a **User Name** with permissions to edit address groups and commit the changes to the firewall, for example, an admin level user name.
12. Enter the **Password** for that user name.

The password should not include non-ASCII special characters.

13. Enter the **Device IP Address**.
14. (Optional) Enter the **Device Port**. The default is **443**.
15. Enter the **Software Version**. This is the Panorama API version, such as 10.1, 10.2, 11.0, or 11.1.

If your software version is 11.1.3, the Panorama API version is 11.1.

16. Enter the **Device Group** you noted above in Adding Device Groups.
17. Enter the **Source IP Group** you created in Adding Address Groups (for example, Stellar_Src).
18. Enter the **Destination IP Group** you created in Adding Address Groups (for example, Stellar_Dst).
19. Click **Next**. The final confirmation tab appears.



20. Click **Submit**.


The new firewall connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

© 2026 Stellar Cyber . All rights reserved.