Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Qualys FIM Connectors 6.0.0

This connector allows Stellar Cyber to ingest logs from Qualys File Integrity Monitoring (FIM) and add the records to the data lake. It integrates with the Qualys FIM API to ingest event data.

The Qualys API allows access to data from the past 15 months. Data older than 15 months cannot be accessed.

Refer to the rate limit information in the Qualys documentation. This connector needs one of the following service levels:

- Standard API Service
- Enterprise API Service
- Premium API Service

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Qualys FIM

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Asset	Syslog	msg_class:
Event	Assets (for Asset)	`qualys_fim_asset`
Ignored Event		`qualys_fim_event`

Content Type	Index	Locating Records

Incident		`qualys_fim_ignored_event`
		`qualys_fim_incident`
		
		msg_origin.source:
		`qualys_fim`
		
		msg_origin.vendor
		`qualys`
		
		msg_origin.category:
		`security_scan`

Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Base URL, Username, and Password

Adding a Qualys FIM Connector

To add a Qualys FIM connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining Qualys FIM Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Qualys FIM credentials:

- Base URL—The Base URL for API access, which you identify by following the guidance in the Qualys documentation. This is an example only:

  `gateway.qg3.apps.qualys.com`


- Username and Password—The username and password credential, for which you send a request to authenticate. Follow the guidance in Qualys - File Integrity Monitoring (FIM)

- Getting Started.


Adding the Connector in Stellar Cyber

To add a Qualys FIM connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Vulnerability Scanner** from the **Category** dropdown.
5. Choose **Qualys FIM** from the **Type** dropdown.



The asterisk (*) indicates a required field.


6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.

10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filt
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Enter the **Base URL** you noted above in Obtaining Qualys FIM Credentials.
13. Enter the **Username** you noted above.
14. Enter the **Password** you noted above.

> The password should not include non-ASCII special characters.

15. Choose the **Content Type** you would like to collect. The logs for **Asset**, **Event**, **Ignored Event**, and **Incident** are supported.

> The **Asset** content type is always selected and cannot be removed from the configuration as it is required for host information.

16. Choose the **Interval (min)**. This is how often the logs are collected.
17. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.

The new connector is immediately active.


Testing the Connector

> In addition to testing for connectivity, the **Test** button for the Qualys FIM connector tests that the Base URL and Username and Password are correct and data requests for the requested content type returns successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:
   - Change the **Indices** to **Syslog**.
   - For **Asset** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.