Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring SonicWall Capture Client Connectors

A SonicWall Capture Client connector allows you to disconnect host, initiate scan, restart machine, or shut down using Stellar Cyber (as long as those hosts are managed by SonicWall Capture Client), and ingest SonicWall Capture Client logs, discover assets, and see vulnerabilities.

There can be any number of SonicWall Capture Client connectors active.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: SonicWall Capture Client

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

ATP
Host
Log
Threat
Vulnerabilities
	Syslog
	Scans
	Assets (for Host)
	Linux
		msg_class:
		`sonicwallcc_<content type>`
		msg_class example:
		`sonicwallcc_atp`

Content Type	Index	Locating Records
		msg_origin.source: `sonicwallcc` msg_origin.vendor: N/A msg_origin.category: `endpoint`

Domain

<Host URL>

where <Host URL> is a variable from the configuration of this connector

Response Actions

Action	Required Fields
Initiate Scan	`device.deviceId` and `device.InstallToken`
Disconnect Host	`device.deviceId` and `device.InstallToken`
Restart Machine	`device.deviceId` and `device.InstallToken`
Shut Down Host	`device.deviceId` and `device.InstallToken`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Host URL, Email, Password, and Sonicwall Tenant ID

Adding a SonicWall Capture Client Connector

To add a SonicWall Capture Client connector:


1. Configure SonicWall log management
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Configuring SonicWall Log Management

You must configure SonicWall log management before you add the connector in Stellar Cyber. You must also have the Tenant ID for an administrative user. MySonicWall credentials are not supported with the APIs.

To get the Tenant ID:


1. Log in to the SonicWall Capture Client console (https://captureclient.sonicwall.com) as an administrative user.
2. Navigate to **Management | TENANT SETTINGS.**
3. Copy the **Tenant ID**.




Adding the Connector in Stellar Cyber

To add a SonicWall Capture Client connector in Stellar Cyber:


1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.
4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **SonicWall Capture Client** from the **Type** dropdown.




   The asterisk (*) indicates a required field.
6. Choose the **Function**: **Collect** to collect logs; **Respond** to enable endpoint actions.

7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



   The asterisk (*) indicates a required field.


12. Enter the **Host URL**.

    For release versions prior to v4.3.4, ensure the URL does not include a trailing "/" symbol.

13. Enter the **Email**.
14. Enter the **Password**.

    The password should not include non-ASCII special characters.

15. Enter the **Sonicwall Tenant ID** you noted above, if you chose **Collect**.
16. Enter the **Interval (min)** if you chose **Collect**. This is how often the logs are collected.
17. Choose the **Content Type** you would like to collect, if you chose **Collect**. The logs for **ATP**, **Host**, **Log**, **Threat**, and **Vulnerabilities** are supported.
18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog** if you chose the **Log** or **Threat** content type.

   The table immediately updates to show ingested Interflow records.

3. Change the **Indices** to **Assets** if you chose the **Host** content type.

   The table immediately updates to show ingested Interflow records. Also, hosts discovered through this connector show SonicWall Capture Client as a data source.

4. Change the **Indices** to **Linux Events** if you chose the **Vulnerabilities** content type.

   The table immediately updates to show ingested Interflow records.

5. Change the **Indices** to **Scans** if you chose the **ATP** content type.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.