Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring SonicWall Firewall Connectors

You can connect Stellar Cyber to firewalls so that you can quickly and easily implement firewall rules on those firewalls from within Stellar Cyber, while you are threat hunting. You can configure firewall actions or manually trigger a firewall action from the event display. For either action you must already have your firewall connected.

Connector Overview: SonicWall Firewall

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP** or **Sensor**
- Interval: **N/A**

Collected Data

N/A

Domain

https://<Device IP Address>:<Device Port>

where <Device IP Address> and <Device Port> are variables from the configuration of this connector

Response Actions

Action	Required Fields
Block IP	`srcip` or `dstip`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- User Name, Password, Device IP Address, Source IP Group, Destination IP Group, and External Zone

Adding a SonicWall Firewall Connector

To add a new SonicWall firewall connector:


1. Configure SonicWall:
    - For **version 7.0** of Sonic OS
    - For **previous versions** of Sonic OS
2. Enable and test the connector in Stellar Cyber:
    a. Add the connector in Stellar Cyber
    b. Test the connector
    c. Verify ingestion

Configuring SonicWall


Configuration in SonicWall v7.0

To enable integration using the v7.0 version of SonicWall:


1. Log in to your SonicWall firewall.
2. Navigate to the **Device** tab from the top of the console.
3. From the left side navigation, select **Firewall > Settings > Administration**.
4. On the pane that displays, select the tab for **Audit / SonicOS API**.
5. In the section for **SONICOS API**, toggle the following options as indicated:
    - **SonicOS API: ON**
    - **CHAP authentication: ON**
    - **RFC-2617 HTTP Basic Access authentication: ON**
    - **Session security using RFC-7616 Digest authentication: OFF**



6. Click **Accept**.
7. Ensure the following are also configured on the server:
    a. Navigate to **Device > Local Users & Groups > Local Groups > Edit User Group**.
    b. Ensure that the group for the user you will be configuring has the following setting enabled.



c. In the event of multiple administrators, when there is preemption by another admin, the user should drop to non-config mode. You can configure this option in the following location: **Device > Administration > Login / Multiple Administrators:**




Only one session can run using the provided credentials. If a user logs into the console through the browser, it impacts the connector. So if a user logs into the console, they should drop to non-config mode.

Creating SonicWall Address Object Groups

The address groups must contain only IPv4 addresses.

1. Log in to your SonicWall firewall.
2. Navigate to the **Object** tab on the top of the console.
3. From the left side navigation, select **Match Objects > Addresses**.
4. In the pane that displays, ensure the **Address Object** sub-tab is displayed, then click **Add**.



5. In the **Address Object Settings** dialog, enter the following:
    a. **Name**: **0.0.0.0_LAN**
    b. **Zone Assignment**: **LAN**
    c. **Type**: **Host**
    d. **IP Address**: **0.0.0.0**
6. Click **Save**.
7. Click **Add** again to repeat this and add a WAN configuration:

a. **Name**: **0.0.0.0_WAN**

b. **Zone Assignment**: **WAN**


c. **Type**: **Host**

d. **IP Address**: **0.0.0.0**

8. Click **Save**.




9. Click the sub-tab for **Address Groups** and select the **Add** button.



10. In the **Add Address Groups** dialog, do the following:

a. Set the **Name** to **Stellar_src_group**.

b. Locate and select the **0.0.0.0_WAN** you just configured from the **Not In Group** list and click the right arrow to add it to the **In Group** list.



11. Click **Save**.
12. Click **Add** again. The **Add Address Object Group** screen appears.
13. Enter the following:

a. Set the **Name** to **Stellar_dst_group**.

b. Locate and select the **0.0.0.0_LAN** you just configured from the **Not In Group** list and click the right arrow to add it to the **In Group** list.


14. Click **Save**.

Creating SonicWall Access Rules


To create SonicWall access rules:

1. Log in to your SonicWall firewall.
2. Navigate to the **Policy** tab on the top of the console.

3. From the left side navigation, select **Rules and Policies > Access Rules**. The existing rules are displayed in a new pane on the right.



4. From the bottom of the new pane, click the **Add** button.
5. In the **Adding Rule** dialog, configure the rule as follows:
    - **Name** : **Stellar_dst_rule**
    - **Action** : **Deny**
    - **SOURCE**:
        - **Zone / Interface: LAN**
        - **Address: Any**
        - **Port/Services: Any**
    - **DESTINATION**:
        - **Zone / Interface: WAN**
        - **Address: Stellar_dst_group**
        - **Port/Services: Any**
6. Click **Add**.



7. Click **Add** again to configure a rule for the source group.
8. Enter the following:
    - **Name** : **Stellar_src_rule**
    - **Action** : **Deny**
    - **SOURCE**:
        - **Zone / Interface: WAN**
        - **Address: Any**
        - **Port/Services: Any**
    - **DESTINATION**:
        - **Zone / Interface: LAN**


- **Address: Stellar_src_group**
- **Port/Services: Any**

9. Click **Add**.
10. Confirm the rules are entered by searching for *Stellar* in the search dialog in the **Access Rules** pane.

Configuration in Sonicwall v6.x:

To enable integration using previous releases of SonicOS:


1. Log in to your SonicWall firewall.
2. Click **Manage**. The management dashboard appears.



3. Under **System Settings**, click **Appliance | Base Settings**.



   The firewall settings page appears.
4. Scroll down to SonicOS API.



5. Click **Enable SonicOS API**.
6. Enable **RFC-7616**, **CHAP**, and **RFC-2617**.
7. Click **Accept**.


The API is now enabled.

Creating SonicWall Address Object Groups

The address groups must contain only IPv4 addresses.

To create SonicWall address object groups:


1. Log in to your SonicWall firewall.
2. Click **Manage**. The management dashboard appears.




3. Under **Policies**, click **Objects | Address Objects**.



   The existing address objects appear.
4. Click **Add**. The **Add Address Object** screen appears.



5. Enter the following:
   a. **Name**: **0.0.0.0_LAN**
   b. **Zone Assignment**: **LAN**
   c. **Type**: **Host**
   d. **IP Address**: **0.0.0.0**
6. Click **OK**.
7. Click **Add** again. The **Add Address Object** screen appears.




8. Enter the following:
   a. **Name**: **0.0.0.0_WAN**
   b. **Zone Assignment**: **WAN**

c. **Type**: **Host**

d. **IP Address**: **(redacted).0**

9. Click **OK**.
10. Click **Address Groups**.
11. Click **Add**. The **Add Address Object Group** screen appears.




12. Enter the following:

a. **Name**: **Stellar_src_group**

b. **In Group**: **0.0.0.0_WAN**

13. Click **OK**.
14. Click **Add** again. The **Add Address Object Group** screen appears.



15. Enter the following:

a. **Name**: **Stellar_dst_group**


b. **In Group**: **0.0.0.0_LAN**

16. Click **OK**.

Creating SonicWall Access Rules

To create SonicWall access rules:

1. Log in to your SonicWall firewall.
2. Click **Manage**. The management dashboard appears.




3. Under **Policies**, click **Rules | Access Rules**.




The existing rules appear.

4. Click **Add**. The **Add Rule** screen appears.



5. Enter the following:
    a. **Policy Name**: **Stellar_dst_rule**
    b. **Action**: **Deny**
    c. **From**: **LAN**
    d. **To**: **WAN**
    e. **Source Port**: **Any**
    f. **Service**: **Any**
    g. **Source**: **Any**
    h. **Destination**: **Stellar_dst_group**
6. Click **Add**.
7. Click **Add** again. The **Add Rule** screen appears.




8. Enter the following:
    a. **Policy Name**: **Stellar_src_rule**
    b. **Action**: **Deny**
    c. **From**: **WAN**
    d. **To**: **LAN**
    e. **Source Port**: **Any**
    f. **Service**: **Any**
    g. **Source**: **Stellar_src_group**
    h. **Destination**: **Any**
9. Click **Add**.


Adding the Connector in Stellar Cyber

To add the SonicWall Firewall connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Firewall** from the **Category** dropdown.
5. Choose **SonicWall Firewall** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

11. Enter the **User Name** to log in to the firewall.
12. Enter the **Password** to log in to the firewall.

    The password should not include non-ASCII special characters.

13. Enter the **Device IP Address**.
14. (Optional) Enter the **Device Port**. The default is **443**.
15. Enter the **Source IP Group** that you created earlier. Our example uses **Stellar_src_group**.
16. Enter the **Destination IP Group** that you created earlier. Our example uses **Stellar_dst_group**.
17. Enter the **External Zone**. This example uses **WAN**.
18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.


The new firewall connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Search for **msg_origin.source: sonicfw**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.