Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

# Configuring Tenable.io Connectors

**Learn more at Stellar Cyber Academy.**

The following link takes you to a course on the Stellar Cyber Academy technical training portal where you can learn more about this topic by watching the suggested lessons.

M03 Modular Sensor Concepts and Configuration (08h:56m)

Modular Sensor Tenable Nessus Scanner (30m:00s)

Explore how the Stellar Cyber Modular Sensor includes a built-in Tenable Nessus vulnerability scanner. Learn how integrated vulnerability scanning simplifies deployment and enables efficient collection of vulnerability data for enhanced security monitoring and analysis.

Modular Sensor Platform Connector with Tenable (50m:00s)

Explore how to configure the Stellar Cyber Platform connector for Tenable.io. Learn to integrate Tenable.io with the Stellar Cyber Platform to automate collection of vulnerability scan and asset data for enhanced threat analysis and reporting.

The first time you access a link on the portal during a session, you must log in to access content.

Vulnerability scanners examine hosts for known and possible security vulnerabilities. You can use this connector to ingest scan reports to the Stellar Cyber data lake.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

## Connector Overview: Tenable.io

### Capabilities

- Collect: **Yes**

- Respond: **No**
- Native Alerts Mapped: **N**
- Runs on: **DP**
- Interval: **Configurable**

### Collected Data

| Content Type | Index | Locating Records |
|---|---|---|
| Vulnerabilities<br>Scans (reports and events) | Scans<br>Assets (for Vulnerabilities) | msg_class:<br>`security_scan`<br>`security_scan_reports`<br><br>msg_origin.source:<br>`tenableio`<br>`tenableio_reports`<br><br>msg_origin.vendor<br>`tenable`<br><br>msg_origin.category:<br>`security_scan` |

### Domain

N/A

### Response Actions

N/A

### Third Party Native Alert Integration Details

N/A

### Required Credentials and Configurations

- Access Key and Secret Key

## Adding a Tenable.io Connector

To add a Tenable.io connector:

1. Obtain Tenable.io credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

## Obtaining Tenable.io Credentials


The following credentials are required:

- Create a user with Administrator privileges.
- Log in as that user to a[redacted]pt the license agreement.
- Add that user to a group with the following permissions: **Can View** and **Can Scan**, and the following access object: **All Assets**.
- Generate API keys.


## Create a User

To create a user:


1. Navigate to **Settings**.





2. Choose **Access Control**.




3. Choose **Users | Create User**.




4. Enter the **FULL NAME**, **USERNAME**, **EMAIL**, **PASSWORD**, and **VERIFY PASSWORD**.





5. Select **Administrator** from the **ROLE** dropdown.
6. Select **API Key** for **AUTHENTICATION**.
7. Click **Next**.
8. Select **All Users** from the **USER GROUPS** dropdown.

9. Click **Next**.
10. Click **Save**.
11. Log in to Tenable.io as that user and accept the license agreement.


## Add Permissions

To add permissions and groups for the user:

1. Navigate to **Settings | Access Control**.
2. Choose **Permissions | Create Permission**.




3. Enter a **PERMISSION NAME** and select the user from the **USERS** drop down.





4. Select the **All Users** group from the **GROUPS** dropdown.
5. Select **Can View** and **Can Scan** from the **PERMISSIONS** dropdown.
6. Select **All Assets** from the **OBJECTS** dropdown.
7. Click **Save**.


## Generate API Keys

To generate API keys:


1. Navigate to **Settings** and choose **My Account**.





2. Select **API KEYS**.




3. Click **Generate**.




4. Click **Continue**.




5. Copy the **ACCESS KEY** and **SECRET KEY**, which will be used to add the connector in Stellar Cyber.


> Store the API keys in a safe location. They cannot be retrieved later although they can be regenerated.

# Adding the Connector in Stellar Cyber


See Tenable for information on configuring a Tenable.io scanner.

To add a new Tenable.io vulnerability scanner connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.




The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Vulnerability Scanner** from the **Category** dropdown.
5. Choose **Tenable.io** from the **Type** dropdown.





The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.


8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Enter the **Access Key** you noted above.
13. Enter the **Secret Key** you noted above.
14. Enter the **Interval**, which is the time between polls of the scanner.

15. Choose **Asset Synchronization** to share information bi-directionally. If you enable this, Stellar Cyber shares MAC-identified assets with Tenable.io.
16. Choose the **Content Type**. The logs for **Scans** and **Vulnerabilities** are supported. Select **Scans** to collect **Security Scan Reports** and **Security Scan Events**.
17. Click **Next**. The final confirmation tab appears.




18. Click **Submit**.


The new connector is immediately active and collects logs for the previous 30 days.

# Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !




Failure with summary of issue:




Show More example detail:




If the test fails, the common HTTP status error codes are as follows:

| HTTP Error Code | HTTP Standard Error Name | Explanation | Recommendation |
|---|---|---|---|
| 400 | Bad Request | This error occurs when there is an error in the connector configuration. | Did you configure the connector correctly? |
| 401 | Unauthorized | This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API. | Did you enter your credentials correctly?<br>Are your credentials expired?<br>Are your credentials entitled or licensed for that specific resource? |
| 403 | Forbidden | This error occurs when the permission or scope is not correct in a valid credential. | Did you enter your credentials correctly?<br>Do you have the required role or permissions for that credential? |
| 404 | Not Found | This error occurs when a URL path does not resolve to an entity. | Did you enter your API URL correctly? |
| 429 | Too Many Requests | This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded. | The server or user license/quota will eventually recover. The connector will periodically retry the query.<br>If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas. |

For a full list of codes, refer to HTTP response status codes.

# Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

- For **Scans** and **Vulnerabilities**, change the **Indices** to **Scans**.
- For **Vulnerabilities** only, change the **Indices** to **Assets**.

The table immediately updates to show ingested Interflow records.

Search for the msg_class values listed in Locating Records at the top of this page.


© 2026 Stellar Cyber . All rights reserved.