Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring ThreatDown OneView Connectors

6.1.0

This connector allows Stellar Cyber to ingest logs from ThreatDown OneView (formerly Malwarebytes OneView) and add the records to the data lake. This connector integrates with the ThreatDown API to query detections and endpoints. It collects assets and detections (endpoint IDs and IP events) from all sites that the API client ID and API Secret have permissions to access.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: ThreatDown OneView

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Detections	Syslog	msg_class: `malwarebytes_oneview_detection`
Endpoints	Assets (for Endpoints)	`malwarebytes_oneview_endpoint` msg_origin.source:

Content Type	Index	Locating Records

		`malwarebytes_oneview`
		
		msg_origin.vendor:
		`malwarebytes`
		
		msg_origin.category:
		`endpoint`
		
		The msg_class, msg_origin.source, and msg_origin.vendor names did not change due to rebranding.

If there is asset information in the logs for Endpoints, the detected assets are reported in the Assets Index.

Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Base URL, Client ID, and Client Secret

Adding a ThreatDown OneView Connector

To add a ThreatDown OneView connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining ThreatDown OneView Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following ThreatDown OneView credentials:

- Base URL—The base URL for API access. The default is https://api.malwarebytes.com.

  Due to the rebranding of Malwarebytes to ThreatDown, an alternate URL is https://api.threatdown.com.

- Client ID and Client Secret—The credentials for authentication.
- (Optional) Account ID—The data associated with only one account under a Tenant Name.

Generating the Client ID and Client Secret

To generate the Client ID and Client Secret:

1. Log in as a Global Administrator or Site Administrator to the OneView Console.
2. Click **Integrate** on the navigation menu on the left.
3. Click **Add +** in the upper right-hand corner.
4. In the Create OAuth Client ID window:
   a. Enter an Application Name.
   b. Select read, write, and/or execute.
   c. Click **Submit**.
   d. Copy the client ID and client secret.

   Store the client secret in a safe location. It cannot be retrieved later although it can be regenerated.
5. Click **OK**.

Locating the Account ID

To locate the Account ID:

- If you are logged into the Nebula site, locate the Account ID in the URL:

  https://cloud.malwarebytes.com/xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx/dashboard


- You can also locate the Account ID in the local activity log:

  C:\ProgramData\Malwarebytes Endpoint Agent\logs\EndpointAgent.txt


Adding the Connector in Stellar Cyber

To add a ThreatDown OneView connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **ThreatDown OneView (formerly Malwarebytes OneView)** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Enter the **Base URL** you noted above in Obtaining ThreatDown OneView Credentials. The default is shown. An alternate URL is https://api.threatdown.com.
13. Enter the **Client ID** you noted above.
14. Enter the **Client Secret** you noted above.
15. (Optional) Enter the **Account ID** you noted above. This is for data associated with only one account under a Tenant Name.

    To retrieve endpoints and detections across all accounts, leave this field blank.

16. Choose the **Interval (min)**. This is how often the logs are collected.
17. Choose the **Content Type** you would like to collect. The logs for **Endpoints** and **Detections** are supported.

    The **Endpoints** content type is always selected and cannot be removed from the configuration as it is required for host information.

18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - For **Detections** and **Endpoints**, change the **Indices** to **Syslog**.
   - For **Endpoints** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.