Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

# Configuring Trellix MVISION Connectors 5.5.0

This connector allows Stellar Cyber to ingest logs from Trellix MVISION and add the records to the data lake. It integrates with the Trellix MVISION EDR API to query for Insight events and devices.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

## Connector Overview: Trellix MVISION

### Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **Yes** 5.5.0
- Runs on: **DP**
- Interval: **Configurable**

### Collected Data

| Content Type | Index | Locating Records |
|---|---|---|
| Alerts 5.5.0<br>Devices<br>Insight Events<br>Threats 5.5.0 | Syslog<br>Assets (for Devices) | msg_class:<br>`trellix_mvision_edr_alerts` 5.5.0<br>`trellix_mvision_insight_devices`<br>`trellix_mvision_insight_events`<br>`trellix_mvision_edr_threats` 5.5.0 |

| Content Type | Index | Locating Records |
| --- | --- | --- |
|  | | msg_origin.source: `trellix_mvision`<br>msg_origin.vendor: `trellix_mvision`<br>msg_origin.category: `endpoint` |

### Domain

N/A

### Response Actions

N/A

### Third Party Native Alert Integration Details 5.5.0

This connector ingests logs from Trellix MVISION to get the raw alerts that are stored in the Syslog index. Select the Alerts content type.

Stellar Cyber maps Trellix MVISION alerts. The alerts are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid` and `trellix_mvision.id`.

For details, see Integration of Third Party Native Alerts.

### Required Credentials and Configurations

- API Key, Client ID, Client Secret, and Scopes

### Locating Records 5.5.0

To search the alerts in the Alerts index or to search the Original Records in the Syslog index, use the query:

- `msg_class: trellix_mvision_edr_alerts AND _exists_: event.threat.name`

# Adding a Trellix MVISION Connector

To add a Trellix MVISION connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

# Obtaining Trellix MVISION Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Trellix MVISION credentials:

- API Key


- Client ID
- Client Secret

The client credentials are available in your Trellix on-boarding email, or see Generating Credentials.


## Generating Credentials

To generate credentials for the APIs needed for the Trellix MVISION connector:


1. Logon to the Trellix Developer portal.





2. Navigate to **Self Service > API Access Information** and click **Configure**.





3. In API Access Information, select the following APIs and Method Types:
    a. For Devices, select GET.





    b. For Events, select GET.





    c. For Insights Events, select GET.





d. For EDR Threats, select GET.





4. Select **Client Credentials**.




5. Click **Add**.
6. Select the Scopes (permissions) for the APIs.




7. Click **Create**.
8. Your Client ID and Secret are generated.





Copy the Client ID and Secret and store them in a safe location. Also copy the Trellix API Key. These credentials are used in the configuration of the Trellix MVISION connector.


## Adding the Connector in Stellar Cyber

To add a Trellix MVISION connector in Stellar Cyber:

1. Log in to Stellar Cyber
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.




   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Trellix MVISION Endpoint Security** from the **Type** dropdown.





   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. This identifies which tenant is allowed to use the connector.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.


12. Enter the **API Key** you noted above in Obtaining Trellix MVISION Credentials.
13. Enter the **Client ID** you noted above.
14. Enter the **Client Secret** you noted above.
15. Enter the **Scopes**, which determine the APIs you are authorized to access. It is a list of permissions for your application. The following is the default scope: epo.device.r mi.user.investigate soc.hts.r soc.rts.r soc.act.tg mi.user.config ins.user ins.suser ins.ms.r
16. Choose the **Interval (min)**. This is how often the logs are collected.

    Trellix MVISION is a rate limited API. An interval of at least 30 minutes is recommended to avoid rate limiting.

17. Choose the **Content Type** you would like to collect. The logs for **Devices**, **Alerts**, **Insight Events**, and **Threats** are supported.

    The **Devices** content type is always selected and cannot be removed from the configuration as it is required for host information.

18. Click **Next**. The final confirmation tab appears.




19. Click **Submit**.


The new connector is immediately active.

# Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !




Failure with summary of issue:




Show More example detail:




If the test fails, the common HTTP status error codes are as follows:

| HTTP Error Code | HTTP Standard Error Name | Explanation | Recommendation |
|---|---|---|---|
| 400 | Bad Request | This error occurs when there is an error in the connector configuration. | Did you configure the connector correctly? |
| 401 | Unauthorized | This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API. | Did you enter your credentials correctly?<br>Are your credentials expired?<br>Are your credentials entitled or licensed for that specific resource? |

| HTTP Error Code | HTTP Standard Error Name | Explanation | Recommendation |
|---|---|---|---|
| 403 | Forbidden | This error occurs when the permission or scope is not correct in a valid credential. | Did you enter your credentials correctly?<br>Do you have the required role or permissions for that credential? |
| 404 | Not Found | This error occurs when a URL path does not resolve to an entity. | Did you enter your API URL correctly? |
| 429 | Too Many Requests | This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded. | The server or user license/quota will eventually recover. The connector will periodically retry the query.<br>If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas. |

For a full list of codes, refer to HTTP response status codes.

# Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - For **Insight Events** and **Devices**, change the **Indices** to **Syslog**.
   - For **Devices** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.


© 2026 Stellar Cyber . All rights reserved.