Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Trend Micro Apex Central Connectors 6.4.0

This connector allows you to discover Trend Micro Apex Central's managed product servers and security agents assets, and add those to the Stellar Cyber data lake for analysis and threat hunting.

This topic refers to configuring a Trend Micro Apex Central connector. Also see:

- Configuring Trend Micro Cloud One Connectors
- Configuring Trend Micro Vision One Connectors

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Trend Micro Apex Central

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Agents	Syslog	msg_class: `trendmicro_apexcentral_agents`
Servers	Assets (for Agents and Servers)	`trendmicro_apexcentral_servers`

Content Type	Index	Locating Records

		msg_origin.source:
		`trendmicro_apexcentral`
		
		msg_origin.vendor:
		`trendmicro`
		
		msg_origin.category:
		`endpoint`

Domain

<User URL>

where <User URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Application ID, API Key, and User URL

Adding a Trend Micro Apex Central Connector

To add a Trend Micro Apex Central connector:


1. Obtain Authentication details for Stellar Cyber integration
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

 Use our example as a guideline, as you might be using a different software version.


Obtaining Authentication Details for Stellar Cyber Integration

Before you add a Trend Micro Connector, you must obtain information that allows the Stellar Cyber connector to authenticate correctly.

1. Log in to the **Trend Micro Apex Central** console as the user who will be associated with the Stellar Cyber app (http://manage.trendmicro.com).
2. When the console has loaded, make note of the redirected URL associated with that user's login:



3. Navigate to **Administration > Settings > Automation API Access Settings**.
4. Click **Add**. The **Application Access Settings** pane displays.
    - **Application Name**: This is to identify the application as being for use with Stellar Cyber
    - **Application ID**: Used by Trend Micro Apex Central to identify Stellar Cyber
    - **API key**: Used by the Stellar Cyber to sign requests sent to Trend Micro Apex Central
    - **API type**: Indicates the API functions that the Stellar Cyber will be using (Isolate/Restore endpoints)
5. Ensure that the checkbox for **Enable application integration using Apex Central Automation APIs** is selected.
6. Configure the following settings.
    - **Application name**: Specify an easily identifiable name for the application.
    - **Communication time-out**: Optionally adjust the number of seconds allowed for a request to reach Trend Micro Apex Central (default is 120 seconds).




7. Note all the information for use later. Click **Save**.

    The Automation API Access Settings screen appears and displays the newly added application in the table.


Adding the Connector in Stellar Cyber

After you have noted the authentication information from the Trend Micro app integration steps, you can add the Trend Micro Apex Central connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose the **Trend Micro Apex Central** connector.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name** for the tenants who will have access to this connector.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Enter the **Application ID**. This is the ID associated with the application you created in Trend Micro Apex Central.

13. Enter the **API Key**. This is the key associated with the application you created in Trend Micro Apex Central.
14. Enter the **User URL**. This is the URL unique to the user whose account was used to create the application in Trend Micro Apex Central.

    For release versions prior to v4.3.4, ensure the URL does not include a trailing "/" symbol.

15. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
16. Choose the **Interval (min)**. This is how often the logs are collected.
17. Choose the **Content Type** you would like to collect. The logs for **Agents** and **Servers** are supported.
18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query.

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
			If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - For **Agents** and **Servers**, change the **Indices** to **Syslog**.
   - For **Agents** and **Servers**, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.