Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Trend Micro Vision One Connectors

The Trend Micro Vision One connector allows you to collect alert details and observed attack techniques from your Trend Micro deployment, and add that to the Stellar Cyber data lake for analysis and threat hunting.

This topic refers to configuring a Trend Micro Vision One connector. Also see:

- Configuring Trend Micro Apex Central Connectors
- Configuring Trend Micro Cloud One Connectors

For API rate limits, refer to the Trend Micro Vision One documentation for API Rate Limit.

In addition, you can use Trend Micro Vision One responders to configure Webhook actions that can be triggered manually or that can enhance Automated Threat Hunting (ATH) actions.

Trend Micro Vision One responders use Webhook templates that support actions. Each action is one responder, there are five actions, and hence there are five Trend Micro Vision One responders: Trend Vision One Add To Block List, Trend Vision One Isolate Endpoint, Trend Vision One Quarantine Email Message, Trend Vision One Remove From Block List, and Trend Vision One Restore Endpoint Connection.

This document describes how to configure a Trend Micro Vision One responder using the Universal Webhook Responder, how to add the respond function to a Trend Micro Vision One connector and how to manually trigger an action and perform ATH actions with a Trend Micro Vision One responder.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Trend Micro Vision One

Capabilities

- Collect: **Yes**
- Respond: **Webhook actions** 6.5.0

- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Alerts
Audit Logs 6.1.0
Observed Attack Techniques
	Syslog	msg_class:
		`trendmicro_visionone_alerts`
		`trendmicro_visionone_audit_logs` 6.1.0
		`trendmicro_visionone_observedattacktechniques`
		msg_origin.source:
		`trendmicro_visionone`
		msg_origin.vendor:
		`trendmicro`
		msg_origin.category:
		`endpoint`

Domain

<API base URL>

where <API base URL> is a variable from the configuration of this connector

Response Actions

Webhook action templates: 6.5.0

- Trend Vision One Add To Block List
- Trend Vision One Isolate Endpoint
- Trend Vision One Quarantine Email Message
- Trend Vision One Remove From Block List
- Trend Vision One Restore Endpoint Connection

Third Party Native Alert Integration Details

This connector ingests logs from Trend Micro Vision One to get the raw alerts that are stored in the Syslog index. Select the Alerts content type.

Stellar Cyber maps Trend Micro Vision One alerts. The alerts are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid` and `trendmicro_visionone.workbenchId`.

Tactic and Technique are provided by the Trend Micro Vision One raw alerts field `trendmicro_visionone.matchedRules`.

For details, see Integration of Third-Party Native Alerts.

Required Credentials and Configurations

- For Collect: API base URL and Bearer token value
- For Respond: Hostname, Protocol, and API Key

Locating Records

To search the alerts in the Alerts index or to search the Original Records in the Syslog index, use the query: `msg_class: trendmicro_visionone_alerts`.

Adding a Trend Micro Vision One Connector

To add a Trend Micro Vision One connector:

1. Obtain credentials (Collect)
2. Obtain credentials (Respond)
3. Add the connector in Stellar Cyber (Collect)
4. Add the connector in Stellar Cyber (Respond)
5. Test the connector
6. Verify ingestion
7. Use actions

Obtaining Credentials (Collect)

Before you configure the connector in Stellar Cyber, you must obtain the following Trend Micro Vision One credentials:

- API Base URL—The base URL for API access. Note the API URL from the location that corresponds to your environment.

Region	FQDN
Australia	api.au.xdr.trendmicro.com
European Union	api.eu.xdr.trendmicro.com
India	api.in.xdr.trendmicro.com
Japan	api.xdr.trendmicro.co.jp
Singapore	api.sg.xdr.trendmicro.com
United States	api.xdr.trendmicro.com

- Bearer token value—The unique, user-generated string of characters required in the Authorization header for API authentication. Refer to the Trend Vision One *API*

Reference document in the following sections: First steps toward using the APIs and Obtain authentication tokens.

Obtaining Credentials (Respond)


Before you configure the connector in Stellar Cyber, you must obtain the following Trend Micro Vision One credentials:

- Hostname—The Hostname for API access. The default is: api.xdr.trendmicro.com. Do not include http or https in the Hostname.
- Protocol—The protocol used by the hostname. The options are HTTP or HTTPS. If you select HTTPS, another field is available: Disable SSL Certificate Verification.
- API Key—The authentication credential. Follow the guidance in the Trend Vision One *API Reference* document in the following sections: First steps toward using the APIs and Obtain authentication tokens.


Adding the Connector in Stellar Cyber (Collect)

After you have noted the authentication information from the Trend Micro app integration, you can add the Trend Micro Vision One connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Trend Micro Vision One** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name** for the tenants who will have access to this connector.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Enter the **API base URL**. Use the table noted in Obtaining Credentials (Collect) to add the appropriate URL for your region.

    For release versions prior to v4.3.4, ensure the URL does not include a trailing "/" symbol.

13. Enter the **Bearer token value**. This is the authentication token you noted in the previous section.
14. Choose the **Interval (min)**. This is how often the logs are collected.

    The logs for **Audit Logs** are queried every 24 hours. 6.1.0

15. Choose the **Content Type** you would like to collect. The logs for **Alerts**, **Audit Logs**, and **Observed Attack Techniques** are supported.
16. Click **Next**. The final confirmation tab appears.




17. Click **Submit**.

The new connector is immediately active.


Adding the Connector in Stellar Cyber (Respond) 6.5.0

To add the respond function for a Trend Micro Vision One connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Webhook** from the **Category** dropdown.
5. Choose one of the predefined templates from the **Type** dropdown: **Trend Vision One Add To Block List**, **Trend Vision One Isolate Endpoint**, **Trend Vision One Quarantine Email Message**, **Trend Vision One Remove From Block List**, and **Trend Vision One Restore Endpoint Connection**.



The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.

7. Enter a **Name**.


   Notes:

   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. This identifies which tenant is allowed to use the connector. In addition to specific tenants, this connector supports **All Tenants**, which means that a Trend Micro Vision One responder can be used across tenants.
9. Choose the device on which to run the connector.

   - Certain connectors can be run on either a Sensor or a Data Processor. The available devices are displayed in the **Run On** menu. If you want to associate your collector with a sensor, you must have configured that sensor prior to configuring the connector or you will not be able to select it during initial configuration.
   - If the device you're connecting to is on premises, we recommend you run on the local sensor. If you're connecting to a cloud service, we recommend you run on the DP.

10. Click **Next**. The **Configuration** tab appears.




    The asterisk (*) indicates a required field.

11. Enter the **Hostname**. The default is api.xdr.trendmicro.com.

    Do not include http or https in the Hostname.

12. Select the **Protocol**, either **HTTP** or **HTTPS**, which is used by the **Hostname**. If you select **HTTPS**, another field is available: **Disable SSL Certificate Verification**.
13. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
14. Enter the **API Key** you noted above in Obtaining Credentials (Respond).
15. Click **Next**. The final confirmation tab, **Done**, appears.



16. Click **Submit**.

Testing the Connector


The **Test** button for the Trend Micro Vision One connector is unable to distinguish between an expired and a non-expired authentication token. As a result, the test will succeed for expired tokens but the connector will fail.

Note that the test button will correctly fail in other cases, such as incorrectly formatted authentication tokens.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

The table immediately updates to show ingested Interflow records.

Using Actions 6.5.0

With a Trend Micro Vision One responder, you can:

- Manually trigger an action
- View action status
- Perform an ATH action


Manually Triggering an Action

To manually trigger an action with a Trend Micro Vision One responder:

1. Select **Threat Hunting**.


   The **Interflow Search** tab appears.

2. Change the **Indices** for the record type, for example, **Syslog**.
3. Scroll down the page and click the icon for **More Info** in the **Actions** column.
4. Click the **Actions** tab. Webhook actions appear under **External Actions**.



5. Click a Trend Micro Vision One Webhook action.

   The template populates the fields in the **Path and Query** and the **JSON Body**.




6. You can modify the **JSON Body** by entering string values or curly brace expressions.
7. To perform the action, click **Submit**.

Viewing Action Status

To view action status:

1. Click **Automation | Action History**.
2. Click **Webhook Actions**.




You can view the action status or error message in the table.

Performing an ATH Action

To perform an ATH action with a Trend Micro Vision One responder:

1. Click **Automation | Automation**.
2. Click **Create**.
3. Scroll down to **Actions**.



4. Click the ➕ button to add an action. Another action appears below the existing action.
5. Select the **Trigger on condition**.
6. Select **Webhook Responder** for the **Type**.
7. Select a previously configured Trend Micro Vision One responder from the dropdown menu for the **Webhook Responder**.

   The template populates the fields in the **Path and Query** and **JSON Body**.
8. You can modify the **JSON Body** by entering string values or curly brace expressions.
9. (Optional) Click **Override Default Settings** to override the playbook's mute settings and mute just this action.
10. Click **Submit**

© 2026 Stellar Cyber . All rights reserved.