Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Versa Networks Firewall Connectors 5.5.0

This is a Beta feature in this release.

You can connect Stellar Cyber to firewalls so that you can quickly and easily implement firewall rules on those firewalls from within Stellar Cyber, while you are threat hunting. You can configure firewall actions or manually trigger a firewall action from the event display.

Connector Overview: Versa Networks Firewall

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **N/A**

Collected Data

N/A

Domain

<Base URL> and <Versa Director URL>

where <Base URL> and <Versa Director URL> are variables from the configuration of this connector

Response Actions

Action	Required Fields
Block IP/Unblock IP	`srcip` or `dstip`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Versa Base URL, Versa Username, Versa Password, Versa Client ID, Versa Director URL, Versa Tenant Name, Versa Organization Name, Versa Template Name, Versa Device UUID, Versa Appliance Name, Versa Source IP Group, and Versa Destination IP Group

Adding a Versa Networks Firewall Connector


To add a Versa Networks firewall connector:

1. Obtain Versa Networks firewall credentials
2. Add the connector in Stellar Cyber
3. Test the connector


Obtaining Versa Networks Firewall Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Versa Networks firewall credentials:


- Versa Base URL—URL for Versa Concerto, which is the same URL used to access the Versa Concerto user interface.
- Versa Username and Versa Password—Username and password for Versa Concerto.
- Versa Client ID—Client ID for Versa Concerto.
- Versa Director URL—URL for Versa Director, which is the same URL used to access the Versa Director user interface, for example, https://www.example.com:9183.
- Versa Tenant Name—Versa Concerto tenant name in which the IP address will be blocked.
- Versa Organization Name—Versa Director organization name that will be used to create/update/get an address group to block an IP address. You can locate it in the Versa Director user interface under **Administration > Organizations**.




- Versa Template Name—Template for Versa Director. You can locate it in the **Configuration > Templates** page of the Versa Director user interface.



- Versa Device UUID—ID of the firewall device. See the procedure in Locating the Device UUID.
- Versa Appliance Name—Firewall appliance name. You can locate it in the Versa Director user interface under **Configuration > Devices**.




- Versa Source IP Group and Versa Destination IP Group—Address groups used to help block or unblock IP addresses. You can locate them in the Versa Director user interface under **Configuration > Templates >** <click on corresponding template name> **Objects and Connectors > Objects > Address Groups**.




Locating the Device UUID

To locate the device UUID:

1. Log in to Versa Concerto.
2. Select **Deploy** and then select **Inspect**.



3. Copy the **Payload** for **publish**.




Adding the Connector in Stellar Cyber


To add a new Versa Networks firewall connector in Stellar Cyber:

1. Log in to Stellar Cyber.

2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Firewall** from the **Category** dropdown.
5. Choose **Versa Networks Firewall** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

11. Enter the **Versa Base URL** you noted above in Obtaining Versa Networks Firewall Credentials.
12. Enter the **Versa Username** you noted above.
13. Enter the **Versa Password** you noted above.
14. Enter the **Versa Client ID** you noted above.
15. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
16. Enter the **Versa Director URL** you noted above.
17. Enter the **Versa Tenant Name** you noted above.
18. Enter the **Versa Organization Name** you noted above.
19. Enter the **Versa Template Name** you noted above.
20. Enter the **Versa Device UUID** you noted above.
21. Enter the **Versa Appliance Name** you noted above.
22. Enter the **Versa Source IP Group** you noted above.
23. Enter the **Versa Destination IP Group** you noted above.
24. Click **Next**. The final confirmation tab appears.



25. Click **Submit**.

The new firewall connector is immediately active.


Testing the Connector

The **Test** button for the Versa Networks Firewall connector verifies login and **Versa Source IP Group**/**Versa Destination IP Group** information. The **Test** button does not verify other fields, for example, **Versa Tenant Name**, **Versa Device UUID**, or **Versa Appliance Name**. However, if those fields are invalid, actions such as Block IP will fail.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

© 2026 Stellar Cyber . All rights reserved.