Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Webroot Connectors

This connector allows Stellar Cyber to ingest logs from Webroot and add the records to the data lake.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Webroot

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Blocked Traffic	Syslog	msg_class: `webroot_blocked_traffic`
Blocked Urls	Assets (for Endpoints)	`webroot_blocked_urls`
Endpoints		`webroot_endpoints`
Phishing		`webroot_phishing`
Threat History		`webroot_threat_history`
Traffic Summary		`webroot_traffic_summary`

Content Type	Index	Locating Records

		msg_origin.source:
		`webroot`
		
		msg_origin.vendor
		`webroot`
		
		msg_origin.category:
		`endpoint`

Domain

https://unityapi.webrootcloudav.com

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Client ID, Client Secret, Username, Password, GSM key (Parent Keycode)

Adding a Webroot Connector

To add a Webroot connector:

1. Obtain Webroot credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion


Obtaining Webroot Credentials

Use the following steps as a guide to obtain the credentials required to allow Stellar Cyber to retrieve data with the Webroot API.


1. Access the Webroot Identity Portal (Management Console) as the username and password you will use to configure the Stellar Cyber connector. Make note of the login information for later use.

   The password should not include non-ASCII special characters.


2. From the left navigation pane, select **Settings.**
3. When the Settings page displays, select the **Unity API Access** sub-tab.




4. Click the button to **Create New Client Credential**.
5. In the dialog that displays, specify a **Name** and **Description** for the credential, then click **Next**.



6. On the next screen, enable the option to use the **event notification API**, specifying **Other use ...** for the Purpose. Then click **Next**.
7. On the final screen, click **Save**.
8. The console displays a dialog with both the **Client ID** and the **Client Secret**. Make note of both of these values. The Client Secret cannot be retrieved later, although it can be regenerated.



9. The final information you need is the **Parent Keycode**, which you will enter as the GSM Key later. Click the sub-tab for **Account Information** and record the value for that field.




10. Review your list of information before proceeding. You should now have:
    - **Username**
    - **Password**
    - **Client ID**
    - **Client Secret**

- **Parent Keycode (GSM key)**


Adding the Connector in Stellar Cyber

With the access information handy, you can add a Webroot connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System** | **INTEGRATIONS** | **Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Webroot** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.


8. Choose a **Tenant Name**. This identifies which tenant is allowed to use the connector.
9. Choose the device on which to run the connector.

10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filt
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the following information you noted from the previous section:
    - Enter the **Client ID**.
    - Enter the **Client Secret**.
    - Enter the **Username** and **Password**.
    - Enter the **GSM Key** (Parent Keycode).
13. Choose the **Interval (min)**. This is how often the logs are collected.
14. Chose the **Content Type**. The following are available:
    - Blocked Urls
    - Blocked Traffic
    - Endpoints
    - Phishing
    - Threat History
    - Traffic Summary
15. Click **Next**. The final confirmation tab appears.



16. Click **Submit**.

The new connector is immediately active.


Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before

performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired?

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Are your credentials entitled or licensed for that specific resource? Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Resolving Error Messages for Webroot Connectors

In certain situations, the initial Test for a Webroot connector may report success but then subsequently display an error message in the **Messages** column of the **System | INTEGRATIONS | Connectors** page. Use the following information to resolve common error messages for Webroot connectors:

- `WSAT is not enabled for this site`

  `"{"statusCode":400,"requestId":"c60683f4-09a7-48c2-ae48-c8df21e8bb90","error":"wsat_not_enabled","error_description":"WSAT is not enabled for this site.","AdditionalInformation":{}}"`

  This error message appears when the Security Awareness Training feature in Webroot is either not enabled or its subscription has expired. Try the following in Webroot:

  - Make sure that **WSAT** is enabled in **Security Awareness Training > Settings > Enable Security Awareness Training**.
  - Make sure the Security Awareness subscription has not expired.

- `DNSP is not enabled for this site`

  `{"statusCode":400,"requestId":"0e12a84d-1123-4c87-937b-a6469ee52b3c","error":"dnsp_not_enabled","error_description":"DNSP is not enabled for this site.","AdditionalInformation":{}}`

  This error message appears when the DNS Protection feature in Webroot is either not enabled or its subscription has expired. Try the following in Webroot:

  - Make sure that the **DNS Protection** subscription in Webroot is not expired.

- Make sure that the **DNS Protection** feature is set to **On** in Webroot.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - For all content types, change the **Indices** to **Syslog**.
   - For **Endpoints** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.