Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring iManage Threat Manager Connectors 6.3.0

This connector allows Stellar Cyber to ingest logs from iManage Threat Manager and add the records to the data lake. It integrates with the iManage Threat Manager API to collect alerts from Behavioral Analytics and Detect and Protect, retrieving alerts from legal document management systems.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: iManage Threat Manager

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Behavioral Analytics Alerts
Detect and Protect Alerts
	Syslog	msg_class:
		`imanage_threat_manager_behavioral_analytics_alerts`
		`imanage_threat_manager_detect_and_protect_alerts`
		
		msg_origin.source:

Content Type	Index	Locating Records

		`imanage_threat_manager`
		
		msg_origin.vendor:
		`imanage`
		
		msg_origin.category:
		`dlp`

Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- For API Token Auth Method: Base URL, API Token, and API Secret
- For User Sign-In Auth Method: Base URL, Username, and Password

Adding an iManage Threat Manager Connector

To add an iManage Threat Manager connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining iManage Threat Manager Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following iManage Threat Manager credentials:

- Base URL—The base URL for API access. The default is https://example.tm-cloudimanage.com/example-api-path
- API Token Auth Method—The **API Token** authentication method:
    - API Token
    - API Secret
- User Sign-In Auth Method—The **User Sign-In** authentication method:
    - Username

- Password


Follow the guidance in the documents: *Integrating iManage Threat Manager alerts into your SIEM application using the iManage Threat Manager API* or *iManage Threat Manager Administration Guide*.

API Token Auth Method

You can generate an application token, consisting of a token and a secret pair, within the iManage Threat Manager admin console.

You need to be in the Integrations Manager role to create an application token.

1. Navigate to **Configuration** > **Settings** > **System** > **New Token**.




User Sign-In Auth Method

You can also use the iManage Threat Manager API with an access token obtained from explicit user credentials. This provides a similar level of access to what you have in the admin console.


Adding the Connector in Stellar Cyber

To add an iManage Threat Manager connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Data Loss Prevention** from the **Category** dropdown.

5. Choose **iManage Threat Manager** from the **Type** dropdown




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.


> Notes:
> - This field does not accept multibyte characters.
> - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Enter the **Base URL** you noted above in Obtaining iManage Threat Manager Credentials.
13. For Auth Method **API Token**:
    a. Enter the **API Token** you noted above.
    b. Enter the **API Secret** you noted above.
14. For Auth Method **User Sign-In**:
    a. Enter the **Username** you noted above.
    b. Enter the **Password** you noted above.



15. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
16. Choose the **Interval (min)**. This is how often the logs are collected.
17. Choose the **Content Type** you would like to collect. The logs for **Behavioral Analytics Alerts** and **Detect and Protect Alerts** are supported. See [Query for Behavioral Analytics Alerts] for information on **Behavioral Analytics Alerts**.

    Use the **User Sign-In** Auth Method to pull the **Detect and Protect Alerts**.
18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.

The new connector is immediately active.

Query for Behavioral Analytics Alerts

For the Behavioral Analytics Alerts, the two different authentication methods use different API endpoints:

- API Token uses /getAlertList. This alert can only be queried using the access token from the **API Token** Auth Method.
- User Sign-In uses /getAddressableAlerts. This alert can only be queried using the access token from the **User Sign-In** Auth Method.

Detect and Protect Alerts can only be obtained with an access token from the **User Sign-In** Auth Method.


Testing the Connector

In addition to testing for connectivity, the **Test** button for the iManage Threat Manager connector tests that the Base URL and authentication are correct and data requests for the requested content types return successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.