#### **NAME**

du – estimate file space usage

### **SYNOPSIS**

```
du [OPTION]... [FILE]...
du [OPTION]... --files0-from=F
```

### DESCRIPTION

Summarize disk usage of each FILE, recursively for directories.

Mandatory arguments to long options are mandatory for short options too.

### -0, --null

end each output line with NUL, not newline

### -a, --all

write counts for all files, not just directories

### --apparent-size

print apparent sizes, rather than disk usage; although the apparent size is usually smaller, it may be larger due to holes in ('sparse') files, internal fragmentation, indirect blocks, and the like

### -B, --block-size=SIZE

scale sizes by SIZE before printing them; e.g., '-BM' prints sizes in units of 1,048,576 bytes; see SIZE format below

#### -b. --bytes

```
equivalent to '--apparent-size --block-size=1'
```

### -c, --total

produce a grand total

### -D, --dereference-args

dereference only symlinks that are listed on the command line

### -d, --max-depth=N

print the total for a directory (or file, with **—-all**) only if it is N or fewer levels below the command line argument; **—-max-depth**=0 is the same as **—-summarize** 

## --files0-from=F

summarize disk usage of the NUL-terminated file names specified in file F; if F is -, then read names from standard input

## -H equivalent to −−dereference−args (−D)

#### -h, --human-readable

print sizes in human readable format (e.g., 1K 234M 2G)

### --inodes

list inode usage information instead of block usage

## $-\mathbf{k}$ like $--\mathbf{block}-\mathbf{size}=1K$

### -L, --dereference

dereference all symbolic links

### -l, --count-links

count sizes many times if hard linked

### -m like --block-size=1M

### -P, --no-dereference

don't follow any symbolic links (this is the default)

## -S, --separate-dirs

for directories do not include size of subdirectories

--si like -h, but use powers of 1000 not 1024

### -s. --summarize

display only a total for each argument

### -t, --threshold=SIZE

exclude entries smaller than SIZE if positive, or entries greater than SIZE if negative

--time show time of the last modification of any file in the directory, or any of its subdirectories

#### --time=WORD

show time as WORD instead of modification time: atime, access, use, ctime or status

### --time-style=STYLE

show times using STYLE, which can be: full-iso, long-iso, iso, or +FORMAT; FORMAT is interpreted like in 'date'

### -X, --exclude-from=FILE

exclude files that match any pattern in FILE

### --exclude=PATTERN

exclude files that match PATTERN

## -x, --one-file-system

skip directories on different file systems

--help display this help and exit

### --version

output version information and exit

Display values are in units of the first available SIZE from —**block**—**size**, and the DU\_BLOCK\_SIZE, BLOCK\_SIZE and BLOCKSIZE environment variables. Otherwise, units default to 1024 bytes (or 512 if POSIXLY CORRECT is set).

The SIZE argument is an integer and optional unit (example: 10K is 10\*1024). Units are K,M,G,T,P,E,Z,Y (powers of 1024) or KB,MB,... (powers of 1000).

### **PATTERNS**

PATTERN is a shell pattern (not a regular expression). The pattern? matches any one character, whereas \* matches any string (composed of zero, one or multiple characters). For example, \*.o will match any files whose names end in .o. Therefore, the command

will skip all files and subdirectories ending in .o (including the file .o itself).

### **AUTHOR**

Written by Torbjorn Granlund, David MacKenzie, Paul Eggert, and Jim Meyering.

### REPORTING BUGS

GNU coreutils online help: <a href="http://www.gnu.org/software/coreutils/">http://www.gnu.org/software/coreutils/</a>

Report du translation bugs to <a href="http://translationproject.org/team/">http://translationproject.org/team/</a>

# **COPYRIGHT**

Copyright © 2014 Free Software Foundation, Inc. License GPLv3+: GNU GPL version 3 or later <a href="http://gnu.org/licenses/gpl.html">http://gnu.org/licenses/gpl.html</a>>.

This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

### **SEE ALSO**

Full documentation at: <a href="http://www.gnu.org/software/coreutils/du">http://www.gnu.org/software/coreutils/du</a> or available locally via: info '(coreutils) du invocation'