

OBS GUI and Config Setting Reference

Generated on 2026-07-23 from dist\OBS\config.ini.

Searchable Directory

Use PDF search for any GUI label, config key, tab, section, or source file. The companion CSV at docs/settings-reference/settings-index.csv contains the same searchable directory in row form.

Repository Reference

Private backup/update repository: NANOBYTECOMPUTERS/obs2.

This reference covers the OpenCV 5 CUDA / TensorRT 11.1 project state after neural, depth, PID, feed-forward, and smart-blending code paths were removed. Local dependency drops under modules/ and extras/ are intentionally excluded from Git and should be restored through the documented build/dependency scripts.

Targeting Pipeline

The runtime path is now detector, tracker, Kalman/IMM state estimation, target-motion state publishing, a paced mouse stream, calibrated pixel-to-count conversion, and mouse output. Detections and tracker observations feed targeting directly without relying on the visual game overlay.

Ego-motion compensation subtracts bounded recent emitted mouse/view motion from tracker priors only. It does not modify raw detections or final mouse output.

Legacy Prediction Compatibility

Deprecated but retained: minSpeedMultiplier, maxSpeedMultiplier, predictionInterval, snapRadius, nearRadius, speedCurveExponent, snapBoostFactor, kalman_warmup_frames, and kalman_acquisition_frames remain loadable for old configs and aim-simulation parity.

Removal gate: remove these only after a behavior baseline proves behavior stays identical across the live tracker, game overlay simulation, and config merge path.

Order	Tab	Notes
1	Capture	Adjustable controls documented below
2	Target	Adjustable controls documented below
3	Mouse	Adjustable controls documented below
4	AI	Adjustable controls documented below
5	Buttons	Adjustable controls documented below
6	Overlay	Adjustable controls documented below
7	Game Overlay	Adjustable controls documented below
8	Stats	Read-only monitor tab
9	Debug	Adjustable controls documented below

Capture Tab

Sliders

Section	Slider	Config key	Range	Current	Notes
General Capture	Capture FPS	capture_fps	0-240	n/a	Limits capture loop FPS. 0 disables the cap path and the GUI warns at 0 or 61+.
Capture Preview	Debug scale	preview_debug_scale	0.1x-2.0x	n/a	Preview-only scale slider. It is not saved to config.ini.
Virtual Camera	Virtual camera width	virtual_camera_width	128-3840	n/a	Applies when capture_method is virtual_camera.
Virtual Camera	Virtual camera heigth	virtual_camera_heigth	128-2160	n/a	Spelling follows the existing config key. Applies when capture_method is virtual_camera.

Activate/Deactivate

Section	Control	Config key	Values	Current	Notes
General Capture	Circle mask	circle_mask	true/false	n/a	Applies the circular capture mask.
General Capture	Use CUDA Direct Capture	capture_use_cuda	true/false	n/a	CUDA/TensorRT builds only. Available with duplication_api capture.
Capture Preview	Show Preview Window	show_window	true/false	n/a	Shows the capture preview/debug frame inside the Capture tab.
WinRT	Capture Borders	capture_borders	true/false	n/a	WinRT capture only. Disabled automatically on unsupported Windows builds.
WinRT	Capture Cursor	capture_cursor	true/false	n/a	WinRT capture only. Includes the cursor in captured frames.

Other GUI-Exposed Config Controls

Section	Control	Config key	Type/options	Current	Notes
General Capture	Detection Resolution	detection_resolution	160, 320, 640	n/a	Changes detector input resolution and restarts/reloads dependent paths.
General Capture	Capture method	capture_method	duplication_api, winrt, virtual_camera, udp_capture	n/a	Selects frame source.
WinRT	Capture target (WinRT)	capture_target	monitor, window	n/a	WinRT only.
WinRT	Window title contains	capture_window_title	text	n/a	Used when WinRT target is window.
Monitor Capture	Capture monitor	monitor_idx	monitor index	n/a	Monitor list is built from active displays.
Virtual Camera	Virtual camera	virtual_camera_name	available cameras	n/a	Filtered list of DirectShow video input devices.
UDP Capture	UDP IP	udp_ip	IPv4/string	n/a	Applied with the Apply UDP Settings button.
UDP Capture	UDP Port	udp_port	1-65535	n/a	Applied with the Apply UDP Settings button.

Target Tab

Sliders

Section	Slider	Config key	Range	Current	Notes
Offsets	Approximate Body Y Offset	body_y_offset	0.05-0.90	n/a	Vertical aim point used for body-class detections.
Offsets	Approximate Head Y Offset	head_y_offset	0.05-0.55	n/a	Vertical aim point used for head-class detections.

Activate/Deactivate

Section	Control	Config key	Values	Current	Notes
Targeting	Disable Headshot	disable_headshot	true/false	n/a	Prevents the head class from being selected as the aim target.
Targeting	Auto Aim	auto_aim	true/false	n/a	Allows target selection/movement logic to act automatically while held conditions are met.

Mouse Tab

Sliders

Section	Slider	Config key	Range	Current	Notes
State Estimator	Acquisition frames	kalman_acquisition_frames	3-5	n/a	Frames used to ramp prediction weight after target acquisition.
State Estimator	Process noise position	kalman_process_noise_position	0.0001-5000	n/a	Position process noise. Higher values adapt faster to position changes.
State Estimator	Process noise velocity	kalman_process_noise_velocity	0.0001-50000	n/a	Velocity process noise. Higher values adapt faster to speed changes.
State Estimator	Measurement noise	kalman_measurement_noise	0.0001-5000	n/a	Measurement noise. Higher values trust detections less.
State Estimator	Velocity damping	kalman_velocity_damping	0.0-3.0	n/a	Damps velocity estimates to reduce runaway prediction.
State Estimator	Max velocity (px/s)	kalman_max_velocity	100-60000	n/a	Maximum allowed tracked velocity.
State Estimator	Warmup frames	kalman_warmup_frames	0-20	n/a	Legacy warmup frames when latency sweep is off.
State Estimator	Additional prediction (ms)	kalman_additional_prediction_ms	-80.0-120.0	n/a	Manual extra prediction offset in milliseconds.
State Estimator	Reset timeout (s)	kalman_reset_timeout_sec	0.05-3.0	n/a	Time without stable observations before estimator state resets.
State Estimator	Ego compensation strength	ego_motion_compensation_strength	0.0-1.0	n/a	Fraction of recent emitted motion subtracted from tracker priors/history to reduce camera-motion jitter.
State Estimator	Ego max shift (px @640)	ego_motion_compensation_max_shift_px	1-128	n/a	Per-frame compensation clamp at 640 detection resolution; scales with detection_resolution.
State Estimator	Ego max age (ms)	ego_motion_compensation_max_age_ms	16-500	n/a	Drops stale emitted-motion samples so compensation fails closed.
Direct Targeting Movement	Deadzone (px)	target_deadzone_px	0.000-20.000	n/a	Minimum target error radius before stream movement is emitted.
Direct Targeting Movement	Stream interval (ms)	target_stream_interval_ms	0.50-8.00	n/a	Paced target-stream wake interval. New tracker observations wake the stream immediately.
Direct Targeting Movement	Stream sharpness	target_stream_sharpness	1.00-80.00	n/a	Time-based convergence factor for the target stream.
Direct Targeting Movement	Max speed (px/s)	target_max_pixel_speed	50-20000	n/a	Maximum pixel-space stream speed before count conversion.
Direct Targeting Movement	State max age (ms)	target_state_max_age_ms	16-500	n/a	Drops stale target-motion snapshots before streaming output.
Direct Targeting Movement	Min stream confidence	target_min_stream_confidence	0.00-0.95	n/a	Minimum confidence required for the target stream to emit movement.
Direct Targeting Movement	Prediction blend	target_prediction_blend	0.000-0.650	n/a	Fraction of bounded short-horizon predicted aim mixed into the observed tracker aim point.
Direct Targeting Movement	Max prediction lead (px)	target_prediction_max_lead_px	0.00-40.00	n/a	Maximum pixel distance the mouse path may lead the current tracker aim point.
Direct Targeting Movement	Governor strength	target_convergence_governor_strength	0.000-1.000	n/a	How strongly the convergence governor can damp or release stream gain from live overshoot, jitter, lock, and ambiguity signals.
Direct Targeting Movement	Governor min gain	target_convergence_governor_min_gain	0.050-1.000	n/a	Lower clamp for governor-scaled stream sharpness and max-step output.
Direct Targeting Movement	Governor max gain	target_convergence_governor_max_gain	1.000-2.000	n/a	Upper clamp for governor-scaled stream sharpness and max-step output.
Direct Targeting Movement	Fallback max step (px/call)	target_max_pixel_step	0.25-120.00	n/a	Legacy per-call clamp for non-stream direct movement helpers and aim-simulation parity.
Direct Targeting Movement	Fallback output scale	target_output_scale	0.010-3.000	n/a	Legacy per-call scale for non-stream direct movement helpers and aim-simulation parity.
Direct Targeting Movement	Signal window samples	target_signal_window_samples	64-2048	n/a	Rolling sample window used for live diagnostic averages and frequency/lag estimates.
Direct Targeting Movement	Signal log interval (ms)	target_signal_log_interval_ms	1.0-1000.0	n/a	Minimum interval between CSV diagnostic rows.
Direct Targeting Movement	Counts / px X	target_counts_per_pixel_x	0.0000-50.0000	n/a	Horizontal calibrated mouse counts per screen-space pixel magnitude.
Direct Targeting Movement	Counts / px Y	target_counts_per_pixel_y	0.0000-50.0000	n/a	Vertical calibrated mouse counts per screen-space pixel magnitude.
Auto Shoot	bScope Multiplier	bScope_multiplier	0.5-2.0	n/a	Multiplier used by auto-shoot scope timing/behavior. Disabled in UI until Auto Shoot is on.

Activate/Deactivate

Section	Control	Config key	Values	Current	Notes
State Estimator	Runtime latency sweep	runtime_latency_sweep_enabled	true/false	n/a	Enables side-by-side latency sweep behavior for estimator comparisons.
State Estimator	Enable Kalman estimator	kalman_enabled	true/false	n/a	Enables Kalman filtering for target motion estimation.

Section	Control	Config key	Values	Current	Notes
State Estimator	Seed velocity on acquire	kalman_velocity_seed_enabled	true/false	n/a	Seeds velocity from early measurement deltas during acquisition.
State Estimator	Compensate detection delay	kalman_compensate_detection_delay	true/false	n/a	Accounts for detector latency in prediction.
State Estimator	Ego-motion compensation	ego_motion_compensation_enabled	true/false	n/a	Opt-in tracker-prior compensation from emitted mouse/view motion. Raw detections and final mouse output are unchanged.
Direct Targeting Movement	Target stream	target_stream_enabled	true/false	n/a	Enables the paced target-motion stream used by the live targeting path.
Direct Targeting Movement	Convergence governor	target_convergence_governor_enabled	true/false	n/a	Enables the optional convergence governor that scales stream gain from live target-lock quality and movement feedback.
Direct Targeting Movement	Target stream debug	target_stream_debug_enabled	true/false	n/a	Shows live target-stream status, prediction, pixel delta, count output, and block reason in the Mouse tab.
Direct Targeting Movement	Target signal diagnostics	target_signal_diagnostics_enabled	true/false	n/a	Shows passive tuning diagnostics for stream cadence, error, output counts, trajectory quality, frequency content, lag, and stability.
Direct Targeting Movement	Signal CSV logging	target_signal_logging_enabled	true/false	n/a	Writes target signal samples to CSV for offline or automatic tuning analysis.
Direct Targeting Movement	Calibrated pixel counts	target_calibrated_pixel_counts_enabled	true/false	n/a	Uses measured counts-per-pixel gains for direct targeting output instead of the default 1:1 pixel-count fallback.
Auto Shoot	Auto Shoot	auto_shoot	true/false	n/a	Enables automatic shooting behavior.
Input Method	Arduino 16-bit Mouse	arduino_16_bit_mouse	true/false	n/a	Arduino input only. Sends wider mouse movement values.
Input Method	Arduino Enable Keys	arduino_enable_keys	true/false	n/a	Arduino input only. Enables keyboard key output through Arduino.

Other GUI-Exposed Config Controls

Section	Control	Config key	Type/options	Current	Notes
Input Method	Mouse Input Method	input_method	WIN32, GHUB, RAZER, DIRECT, ARDUINO, TEENSY41, TEENSY41_HID, KMBOX_NET, KMBOX_A, MAKCU	n/a	Changes active mouse backend.
Input Method	Arduino/Teensy Port	arduino_port	COM1-COM30	n/a	Arduino and Teensy 4.1 serial input.
Input Method	Arduino/Teensy Baudrate	arduino_baudrate	9600-115200	n/a	Arduino and Teensy 4.1 serial input.
Input Method	Kmbox Net IP	kmbox_net_ip	text	n/a	Saved with Save & Reconnect.
Input Method	Kmbox Net Port	kmbox_net_port	text	n/a	Saved with Save & Reconnect.
Input Method	Kmbox Net UUID	kmbox_net_uuid	text	n/a	Saved with Save & Reconnect.
Input Method	Kmbox A PIDVID	kmbox_a_pidvid	PPPPVVVV	n/a	Saved with Save & Reconnect.
Input Method	Makcu Port	makcu_port	AUTO, COM1-COM30	n/a	Makcu input only.
Input Method	Makcu Baudrate	makcu_baudrate	115200-4000000	n/a	Makcu input only.

AI Tab

Sliders

Section	Slider	Config key	Range	Current	Notes
Detection	Confidence Threshold	confidence_threshold	0.01-1.00	n/a	Minimum detector confidence accepted as a detection.
Detection	NMS Threshold	nms_threshold	0.00-1.00	n/a	Non-max suppression overlap threshold.
Detection	Max Detections	max_detections	1-100	n/a	Maximum detections retained after model output processing.

Activate/Deactivate

No activate/deactivate checkboxes in this tab.

Other GUI-Exposed Config Controls

Section	Control	Config key	Type/options	Current	Notes
Model	Model	ai_model	models folder	n/a	Selects detector model from available files.
Backend	Backend	backend	TRT, DML	n/a	CUDA builds only; DML build does not expose this combo.

Buttons Tab

Sliders

No saved GUI sliders in this tab.

Activate/Deactivate

Section	Control	Config key	Values	Current	Notes
Arrow Key Options	Enable arrows keys options	enable_arrows_settings	true/false	n/a	Allows arrow-key adjustment of target offsets.

Other GUI-Exposed Config Controls

Section	Control	Config key	Type/options	Current	Notes
Button Bindings	Targeting Buttons	button_targeting	key list	n/a	Supports multiple bindings with + and -.
Button Bindings	Shoot Buttons	button_shoot	key list	n/a	Supports multiple bindings with + and -.
Button Bindings	Zoom Buttons	button_zoom	key list	n/a	Supports multiple bindings with + and -.
Button Bindings	Exit Buttons	button_exit	key list	n/a	Supports multiple bindings with + and -.
Button Bindings	Pause Buttons	button_pause	key list	n/a	Supports multiple bindings with + and -.
Button Bindings	Reload Config Buttons	button_reload_config	key list	n/a	Supports multiple bindings with + and -.
Button Bindings	Overlay Buttons	button_open_overlay	key list	n/a	Supports multiple bindings with + and -.

Overlay Tab

Sliders

Section	Slider	Config key	Range	Current	Notes
Visual	Overlay Opacity	overlay_opacity	220-255	n/a	Window opacity. The UI clamps to a readable minimum of 220.
Visual	UI Fine Scale	overlay_ui_scale	0.85-1.35	n/a	Fine-grained scaling for the overlay UI.

Activate/Deactivate

Section	Control	Config key	Values	Current	Notes
Capture Privacy	Hide Overlays From Recording	overlay_exclude_from_capture	true/false	n/a	Applies capture exclusion so overlay windows are hidden from supported recording/capture paths.

Other GUI-Exposed Config Controls

Section	Control	Config key	Type/options	Current	Notes
Config	Save Config	config.ini	writes config.ini	n/a	Immediately writes the current runtime config.
Config	Load Config	config.ini	reads config.ini	n/a	Merges config.ini into current runtime values and refreshes runtime-sensitive paths.

Game Overlay Tab

Sliders

Section	Slider	Config key	Range	Current	Notes
General	Overlay Max FPS (0 = uncapped)	game_overlay_max_fps	0-256	n/a	Caps game overlay render rate. 0 is uncapped.
Box Color	A	game_overlay_box_a	0-255	n/a	Detection box alpha.
Box Color	R	game_overlay_box_r	0-255	n/a	Detection box red channel.
Box Color	G	game_overlay_box_g	0-255	n/a	Detection box green channel.
Box Color	B	game_overlay_box_b	0-255	n/a	Detection box blue channel.
Box Color	Box Thickness	game_overlay_box_thickness	0.5-10.0	n/a	Detection box line thickness.
Capture Frame	A	game_overlay_frame_a	0-255	n/a	Capture frame alpha.
Capture Frame	R	game_overlay_frame_r	0-255	n/a	Capture frame red channel.
Capture Frame	G	game_overlay_frame_g	0-255	n/a	Capture frame green channel.
Capture Frame	B	game_overlay_frame_b	0-255	n/a	Capture frame blue channel.
Capture Frame	Frame Thickness	game_overlay_frame_thickness	0.5-10.0	n/a	Capture frame line thickness.
Future Point Style	Point Radius	game_overlay_future_point_radius	1.0-20.0	n/a	Radius of future-position points.
Future Point Style	Point Step Alpha Falloff	game_overlay_future_alpha_falloff	0.10-5.00	n/a	Controls how quickly future-point alpha fades along the path.
Icon Overlay	Icon Width	game_overlay_icon_width	4-512	n/a	Icon width in pixels.
Icon Overlay	Icon Height	game_overlay_icon_height	4-512	n/a	Icon height in pixels.
Icon Overlay	Icon Offset X	game_overlay_icon_offset_x	-500.0-500.0	n/a	Horizontal icon offset from the selected anchor.
Icon Overlay	Icon Offset Y	game_overlay_icon_offset_y	-500.0-500.0	n/a	Vertical icon offset from the selected anchor.
Aim Simulation	Sim X	aim_sim_x	-3000-3000	n/a	Aim simulation window X position.
Aim Simulation	Sim Y	aim_sim_y	-3000-3000	n/a	Aim simulation window Y position.
Aim Simulation	Sim Width	aim_sim_width	220-1600	n/a	Aim simulation window width.
Aim Simulation	Sim Height	aim_sim_height	180-1000	n/a	Aim simulation window height.
Aim Simulation	Sim FPS Min	aim_sim_fps_min	15-360	n/a	Minimum simulated frame rate.
Aim Simulation	Sim FPS Max	aim_sim_fps_max	15-360	n/a	Maximum simulated frame rate. The GUI keeps min and max ordered.
Aim Simulation	FPS Jitter	aim_sim_fps_jitter	0.000-0.800	n/a	Randomized FPS variance for the simulation.
Aim Simulation	Capture Delay (ms)	aim_sim_capture_delay_ms	0.0-80.0	n/a	Simulated capture delay.
Aim Simulation	Inference Delay (ms)	aim_sim_inference_delay_ms	0.0-120.0	n/a	Manual simulated inference delay when not using live timing.
Aim Simulation	Input Delay (ms)	aim_sim_input_delay_ms	0.0-60.0	n/a	Simulated input delay.
Aim Simulation	Extra Delay (ms)	aim_sim_extra_delay_ms	0.0-60.0	n/a	Additional simulated processing delay.
Aim Simulation	Target Max Speed	aim_sim_target_max_speed	20-2500	n/a	Maximum simulated target speed.
Aim Simulation	Target Accel	aim_sim_target_accel	20-10000	n/a	Simulated target acceleration.
Aim Simulation	Target Stop Chance	aim_sim_target_stop_chance	0.00-0.95	n/a	Probability that the simulated target pauses during a retarget.

Activate/Deactivate

Section	Control	Config key	Values	Current	Notes
General	Enable	game_overlay_enabled	true/false	n/a	Enables the separate game overlay renderer.
General	Draw Detection Boxes	game_overlay_draw_boxes	true/false	n/a	Shows detection boxes in the game overlay.
General	Draw Future Positions	game_overlay_draw_future	true/false	n/a	Shows predicted future target points.
General	Draw Wind Debug Tail	game_overlay_draw_wind_tail	true/false	n/a	Shows the wind-mouse debug trail when wind motion is active.
General	Show Target Correction	game_overlay_show_target_correction	true/false	n/a	Shows correction indicators for target prediction/aim adjustment.
Capture Frame	Draw Capture Frame	game_overlay_draw_frame	true/false	n/a	Draws the capture frame rectangle.
Icon Overlay	Enable Icon Overlay	game_overlay_icon_enabled	true/false	n/a	Enables drawing an icon relative to detections.

Section	Control	Config key	Values	Current	Notes
Aim Simulation	Enable Aim Simulation Window	aim_sim_enabled	true/false	n/a	Shows the aim simulation overlay window.
Aim Simulation	Use Live Inference Delay	aim_sim_use_live_inference	true/false	n/a	Uses live backend timing for inference delay instead of the manual value.
Aim Simulation	Show Delayed Observation	aim_sim_show_observed	true/false	n/a	Shows delayed target observation in the simulation.
Aim Simulation	Show Trajectory History	aim_sim_show_history	true/false	n/a	Shows historical target/aim trails.
Aim Simulation	Show Kalman Debug	aim_sim_show_kalman_debug	true/false	n/a	Shows Kalman-related debug visuals in the simulation.

Other GUI-Exposed Config Controls

Section	Control	Config key	Type/options	Current	Notes
Icon Overlay	Icon Path	game_overlay_icon_path	path	n/a	Image path for icon overlay.
Icon Overlay	Icon Class (-1 = all)	game_overlay_icon_class	-1 or class id	n/a	Restricts icon to one class when ≥ 0 .
Icon Overlay	Icon Anchor	game_overlay_icon_anchor	center, top, bottom, head	n/a	Anchor point used for icon placement.

Stats Tab

The Stats tab is read-only in the current GUI. It displays timing graphs, capture FPS, capture details, and CUDA status where available.

Debug Tab

Sliders

No saved GUI sliders in this tab.

Activate/Deactivate

Section	Control	Config key	Values	Current	Notes
Screenshot Buttons	Verbose console output	verbose	true/false	n/a	Enables extra console logging.
Log File	Enable log file	debug_log_file_enabled	true/false	n/a	Writes logs to debug_log_file_path when enabled.

Other GUI-Exposed Config Controls

Section	Control	Config key	Type/options	Current	Notes
Screenshot Buttons	Screenshot buttons	screenshot_button	key list	n/a	Supports multiple bindings with + and -.
Screenshot Buttons	Screenshot delay	screenshot_delay	step 50/500	n/a	Delay before screenshot capture.
Log File	Log file path	debug_log_file_path	path	n/a	Used when Enable log file is on.

Config.ini Settings Not In The GUI

These settings are editable by changing config.ini directly. Some are build-gated: CUDA rows are emitted only by CUDA builds.

Section	Setting	Current/default	Range/options	Visibility	Guidance	Notes
Mouse prediction	prediction_futurePositions	20	integer	Config only	Number of future target positions to retain/use for prediction visualization.	Saved in current config.ini, but no direct GUI control exists.
Mouse prediction	draw_futurePositions	true	true/false	Config only	Enables drawing future positions in preview/debug paths.	Separate from game_overlay_draw_future.
AI backend	backend	DML	DML or TRT	DML config-only / CUDA GUI	Selects DirectML or TensorRT backend.	GUI combo exists only in CUDA builds.
AI backend	dml_device_id	0	integer adapter id	Config only	DirectML adapter index used by ONNX Runtime DML.	Not exposed in the GUI.
System reserves	cpuCoreReserveCount	4	integer	Config only	CPU cores reserved away from worker assignment.	Not exposed in the GUI.
System reserves	systemMemoryReserveMB	2048	MB	Config only	System memory reserve used by runtime resource planning.	Not exposed in the GUI.
Custom classes	class_player	0	integer class id	Config only	Detector class id treated as player/body.	Not exposed in the GUI.
Custom classes	class_head	1	integer class id	Config only	Detector class id treated as head.	Not exposed in the GUI.
Debug	show_fps	false	true/false	Config only	Legacy/debug FPS display flag.	Saved in config.ini but not exposed in the current GUI.
Advanced mouse	minSpeedMultiplier	0.1	float	Loadable hidden key	Legacy minimum movement speed multiplier.	Loadable from config.ini if added manually; saveConfig does not currently emit it.
Advanced mouse	maxSpeedMultiplier	0.1	float	Loadable hidden key	Legacy maximum movement speed multiplier.	Loadable from config.ini if added manually; saveConfig does not currently emit it.
Advanced mouse	predictionInterval	0.01	seconds	Loadable hidden key	Prediction sample interval used by legacy/auxiliary prediction logic.	Loadable from config.ini if added manually; saveConfig does not currently emit it.
Legacy snap	snapRadius	1.5	float	Config only	Legacy snap radius.	Loadable hidden key; no GUI control.
Legacy snap	nearRadius	25.0	float	Config only	Legacy near-target radius.	Loadable hidden key; no GUI control.
Legacy snap	speedCurveExponent	3.0	float	Config only	Legacy speed curve exponent.	Loadable hidden key; no GUI control.
Legacy snap	snapBoostFactor	1.15	float	Config only	Legacy snap boost multiplier.	Loadable hidden key; no GUI control.
Legacy recoil	easynorecoil	false	true/false	Config only	Legacy recoil helper flag.	Loadable hidden key; no GUI control and not emitted by saveConfig.
Legacy recoil	easynorecoilstrength	0.0	float	Config only	Legacy recoil helper strength.	Loadable hidden key; no GUI control and not emitted by saveConfig.
Wind mouse	wind_mouse_enabled	false	true/false	Config only	Enables wind-style motion noise in supported runtime/simulation paths.	Loadable hidden key; no GUI control.
Wind mouse	wind_G	18.0	float	Config only	Wind mouse gravity parameter.	Loadable hidden key; no GUI control.
Wind mouse	wind_W	15.0	float	Config only	Wind mouse wind parameter.	Loadable hidden key; no GUI control.
Wind mouse	wind_M	10.0	float	Config only	Wind mouse max-step parameter.	Loadable hidden key; no GUI control.
Wind mouse	wind_D	8.0	float	Config only	Wind mouse damping/distance parameter.	Loadable hidden key; no GUI control.
CUDA	export_enable_fp8	false	true/false	CUDA config-only	Enables FP8 TensorRT export where supported.	CUDA builds only; no GUI checkbox.
CUDA	export_enable_fp16	true	true/false	CUDA config-only	Enables FP16 TensorRT export where supported.	CUDA builds only; no GUI checkbox.
CUDA	use_cuda_graph	false	true/false	CUDA config-only	Enables CUDA graph execution path.	CUDA builds only; no GUI checkbox.
CUDA	use_pinned_memory	true	true/false	CUDA config-only	Uses pinned host memory for CUDA paths.	CUDA builds only; no GUI checkbox.
CUDA	gpuMemoryReserveMB	2048	MB	CUDA config-only	GPU memory reserve for CUDA resource planning.	CUDA builds only; no GUI control.
CUDA	enableGpuExclusiveMode	true	true/false	CUDA config-only	Attempts GPU exclusive mode at startup.	CUDA builds only; no GUI checkbox.

Source Map

Area	Source
Tab order	overlay/overlay.cpp
Capture	overlay/draw_capture.cpp and overlay/draw_debug.cpp
Target	overlay/draw_target.cpp
Mouse	overlay/draw_mouse.cpp
Buttons	overlay/draw_buttons.cpp
Overlay	overlay/draw_overlay.cpp
Game Overlay	overlay/draw_game_overlay.cpp
Debug	overlay/draw_debug.cpp
Config load/save/defaults	config/config.cpp and config/config.h