OpenDrive

Paths are specified as remote:path

Paths may be as deep as required, e.g. remote:directory/subdirectory.

Here is an example of how to make a remote called remote. First run:

```
rclone config
```

This will guide you through an interactive setup process:

```
n) New remote
d) Delete remote
q) Quit config
e/n/d/q > n
name> remote
Type of storage to configure.
Choose a number from below, or type in your own value
[snip]
XX / OpenDrive
  \ "opendrive"
[snip]
Storage> opendrive
Username
username>
Password
y) Yes type in my own password
g) Generate random password
Enter the password:
password:
Confirm the password:
password:
[remote]
username =
password = *** ENCRYPTED ***
y) Yes this is OK
e) Edit this remote
d) Delete this remote
y/e/d>y
```

List directories in top level of your OpenDrive

```
rclone 1sd remote:
```

List all the files in your OpenDrive

```
rclone ls remote:
```

To copy a local directory to an OpenDrive directory called backup

```
rclone copy /home/source remote:backup
```

Modified time and MD5SUMs

OpenDrive allows modification times to be set on objects accurate to 1 second. These will be used to detect whether objects need syncing or not.

Restricted filename characters

Character	Value	Replacement
NUL	0x00	NUL
1	0x2F	/
"	0x22	11
*	0x2A	*
:	0x3A	:
<	0x3C	<
>	0x3E	>
?	0x3F	?
\	0x5C	\
	0x7C	

File names can also not begin or end with the following characters. These only get replaced if they are the first or last character in the name:

Character	Value	Replacement
SP	0x20	SP
HT	0x09	нт
LF	0x0A	LF
VT	0x0B	VT
CR	0x0D	CR

Invalid UTF-8 bytes will also be replaced, as they can't be used in JSON strings.

Standard Options

Here are the standard options specific to opendrive (OpenDrive).

--opendrive-username

Username

· Config: username

• Env Var: RCLONE_OPENDRIVE_USERNAME

Type: stringDefault: ""

--opendrive-password

Password.

NB Input to this must be obscured - see <u>rclone obscure</u>.

· Config: password

Env Var: RCLONE_OPENDRIVE_PASSWORD

Type: stringDefault: ""

Advanced Options

Here are the advanced options specific to opendrive (OpenDrive).

--opendrive-encoding

This sets the encoding for the backend.

See: the encoding section in the overview for more info.

· Config: encoding

• Env Var: RCLONE OPENDRIVE ENCODING

Type: MultiEncoder

· Default:

Slash,LtGt,DoubleQuote,Colon,Question,Asterisk,Pipe,BackSlash,LeftSpace,LeftCrLfHtVt,RightSpace,RightCrLfHtVt,InvalidUtf8,Dot

--opendrive-chunk-size

Files will be uploaded in chunks this size.

Note that these chunks are buffered in memory so increasing them will increase memory use.

· Config: chunk_size

• Env Var: RCLONE_OPENDRIVE_CHUNK_SIZE

Type: SizeSuffixDefault: 10M

Limitations

Note that OpenDrive is case insensitive so you can't have a file called "Hello.doc" and one called "hello.doc".

There are quite a few characters that can't be in OpenDrive file names. These can't occur on Windows platforms, but on non-Windows platforms they are common. Rolone will map these names to and from an identical looking unicode equivalent. For example if a file has a ? in it will be mapped to ? instead.

rclone about is not supported by the OpenDrive backend. Backends without this capability cannot determine free space for an rclone mount or use policy mfs (most free space) as a member of an rclone union remote.