在 Windows 上安装 Unified Manager

Active IQ Unified Manager

NetApp
May 05, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/active-iq-unified-manager/install-windows/task_install_unified_manager_on_windows.html on May 05, 2022. Always check docs.netapp.com for the latest.

目录

在 Windows 上安装 Unified Manager 1
安装 Unified Manager 1
执行 Unified Manager 的无人参与安装 2

在 Windows 上安装 Unified Manager

请务必了解在 Windows 上下载和安装 Unified Manager 的步骤顺序。

安装 Unified Manager

您可以安装 Unified Manager 来监控数据存储容量，可用性，性能和保护问题并对其进行故障排除。

- 您需要的内容 *
- 您计划安装 Unified Manager 的系统应满足系统和软件要求。

  "硬件系统要求"

  "Windows 软件和安装要求"

  > 从 Unified Manager 9.5 开始， OpenJDK 会随安装包提供并自动安装。从 Unified Manager 9.5 开始，不支持 Oracle Java 。

- 您应具有 Windows 管理员权限。确保您的用户名不以感叹号 "` ！ ` " 开头。如果运行此安装的用户名以 "` ！ ` " 开头，则安装 Unified Manager 可能会失败。
- 您应具有受支持的 Web 浏览器。
- Unified Manager 维护用户密码应介于 8 到 20 个字符之间，并应包含大写字母或小写字母，数字和特殊字符。
- 维护用户或 MySQL root 用户的密码字符串不允许包含以下特殊字符： " ' ` % ， = & < > = ^ \ / （） [ ] ； ：

  允许使用以下特殊字符： ~ ！ @ # $ * - ？ 。 +

步骤

1. 使用默认本地管理员帐户登录到 Windows 。
2. 登录到 NetApp 支持站点，然后导航到 Unified Manager 的 Download 页面：

   "NetApp 支持站点"

3. 选择所需的 Unified Manager 版本并接受最终用户许可协议（ EULA ）。
4. 将 Unified Manager Windows 安装文件下载到 Windows 系统上的目标目录。
5. 导航到安装文件所在的目录。
6. 右键单击并以管理员身份运行 Unified Manager 安装程序可执行文件（ .exe ）。

   Unified Manager 会检测缺少的或预先安装的第三方软件包并列出它们。如果系统中未安装所需的第三方软件包，则 Unified Manager 会在安装过程中安装这些软件包。

7. 单击 * 下一步 * 。
8. 输入用户名和密码以创建维护用户。

9. 在 Database Connection 向导中，输入 MySQL root 密码。
10. 单击 * 更改 * 为 Unified Manager 安装目录和 MySQL 数据目录指定新位置。

    如果不更改安装目录， Unified Manager 将安装在默认安装目录中。

11. 单击 * 下一步 * 。
12. 在准备安装 Shield 向导中，单击 * 安装 * 。
13. 安装完成后，单击 * 完成 * 。
14. 如果您的Windows系统上安装了活动防病毒软件、请在安装完成后手动从防病毒扫描中排除以下路径：
    - Unified Manager 数据目录
    - Unified Manager 安装目录
    - MySQL 数据目录

此安装将创建多个目录：

- 安装目录

  这是您在安装期间指定的 Unified Manager 的根目录。示例： `C ： \Program Files\NetApp\`

- MySQL 数据目录

  这是存储 MySQL 数据库的目录，您在安装期间指定了该目录。示例： `C ： \ProgramData\MySqlServerData\`

- Java 目录

  这是安装 OpenJDK 的目录。示例： `C ： \Program Files\NetApp\JDK\`

- Unified Manager 应用程序数据目录（ appDataDir ）

  此目录用于存储应用程序生成的所有数据。其中包括日志，支持包，备份以及所有其他附加数据。示例： `C ： \ProgramData\NetApp\OnCommandAppData\`

您可以访问 Web UI 以执行 Unified Manager 的初始设置，如中所述 "《 Active IQ Unified Manager 系统配置指南》"。

执行 Unified Manager 的无人参与安装

您可以使用命令行界面安装 Unified Manager ，而无需用户干预。您可以通过将参数以键值对的形式传递来完成无人值守安装。

步骤

1. 使用默认本地管理员帐户登录到 Windows 命令行界面。
2. 导航到要安装 Unified Manager 的位置，然后选择以下选项之一：

选项	说明

如果已预安装第三方软件包	`ActiveIQUnifiedManager-x.y.exe /V"mysql_password=mysql_password INSTALLDIR=\" 安装目录 \" mysql_data_DIR=\"MySQL 数据目录 \" maintenance_password=maintenance_password maintenance_username=maintenance_username /qn /l* v CompletePathForLogFile"`
	
	• 示例：*
	
	`ActiveIQUnifiedManager.exe /s /v"mysql_password=netapp21 ! INSTALLDIR="C ： \Program Files\NetApp" MySql_data_DIR="C ： \ProgramData\MySQLServer\" maintenance_password=` **`maintenance_username=admin /qn /l`** `v C ： \install.log`

如果未安装第三方软件包	`ActiveIQUnifiedManager-x.y.exe /V"mysql_password=mysql_password INSTALLDIR=\" 安装目录 \" mysql_data_DIR=\"MySQL 数据目录 \" maintenance_password=maintenance_password maintenance_username=maintenance_username /qr /l* v CompletePathForLogFile"`
	
	• 示例：*
	
	`ActiveIQUnifiedManager.exe /s /v"mysql_password=netapp21 ! INSTALLDIR="C ： \Program Files\NetApp" MySql_data_DIR="C ： \ProgramData\MySQLServer\" maintenance_password=` **`maintenance_username=admin /QR /l`** `v C ： \install.log`

` /QR` 选项可通过精简的用户界面启用静默模式。此时将显示一个基本用户界面，其中显示了安装进度。系统不会提示您输入。如果未预安装 JRE ， MySQL 和 7zip 等第三方软件包，则应使用 ` /QR` 选项。如果在未安装第三方软件包的服务器上使用 ` /qn` 选项，则安装将失败。

` /qn` 选项可在无用户界面的情况下启用静默模式。安装期间不会显示任何用户界面或详细信息。如果未安装第三方软件包，则不应使用 ` /qn` 选项。

3. 使用以下 URL 登录到 Unified Manager Web 用户界面：

` https://IP 地址`

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.