# Nginx Data Collector

## Cloud Insights

Tony Lavoie, Dave Grace
August 24, 2020

This PDF was generated from https://docs.netapp.com/us-en/cloudinsights/task_config_telegraf_nginx.html on July 21, 2021. Always check docs.netapp.com for the latest.

# Table of Contents

Nginx Data Collector . . . 1
Installation . . . 1
Setup . . . 2
Objects and Counters . . . 2
Troubleshooting . . . 3

# Nginx Data Collector

Cloud Insights uses this data collector to gather metrics from Nginx.

## Installation

1. From **Admin > Data Collectors**, click **+Data Collector**. Under **Services**, choose Nginx.

   Select the Operating System or Platform on which the Telegraf agent is installed.

2. If you haven't already installed an Agent for collection, or you wish to install an Agent for a different Operating System or Platform, click *Show Instructions* to expand the Agent installation instructions.
3. Select the Agent Access Key for use with this data collector. You can add a new Agent Access Key by clicking the **+ Agent Access Key** button. Best practice: Use a different Agent Access Key only when you want to group data collectors, for example, by OS/Platform.
4. Follow the configuration steps to configure the data collector. The instructions vary depending on the type of Operating System or Platform you are using to collect data.



## Follow Configuration Steps

Need Help?

1. If you already have a URL enabled to provide Nginx metrics, go directly to the plugin configuration.

2. Nginx metrics are available through a status page when the HTTP stub status module is enabled.Refer to the below link for verifying/enabling http_stub_status_module.

```
http://nginx.org/en/docs/http/ngx_http_stub_status_module.html
```

3. After verifying the module is enabled ,modify the Nginx configuration to set up a locally-accessible URL for the status page:

```
server {
   listen   <PORT NUMBER>;
   Please specify actual machine IP address, and refrain from using a loopback address (i.e.
localhost or 127.0.0.1)
   server_name  <IP ADDRESS>;
   location /nginx_status {
```

4. Reload the configuration:

```
nginx -s reload
```

5. Copy the contents below into a new .conf file under the /etc/telegraf/telegraf.d/ directory. For example, copy the contents to the /etc/telegraf/telegraf.d/cloudinsights-nginx.conf file.

```
    [[inputs.nginx]]
      ## USER-ACTION: Provide Nginx status url
      ## Please specify actual machine IP address where nginx_status is enabled, and refrain from
using a loopback address (i.e. localhost or 127.0.0.1).
      ## When configuring with multiple Nginx servers, enter them in the format ["url1" ,"url2",
```

6. Replace <INSERT_NGINX_ADDRESS> with the applicable Nginx address. Please specify a real machine address, and refrain from using a loopback address.

7. Replace <INSERT_NGINX_PORT> with the applicable Nginx port.

8. Restart the Telegraf service.

```
systemctl restart telegraf
```

# Setup

Nginx metric collection requires that Nginx http_stub_status_module be enabled.

Additional information may be found in the Nginx documentation.

# Objects and Counters

The following objects and their counters are collected:

| Object: | Identifiers: | Attributes: | Datapoints: |
| --- | --- | --- | --- |
| Nginx | Namespace<br>Server | Node IP<br>Node Name<br>Port | Accepts<br>Active<br>Handled<br>Reading<br>Requests<br>Waiting<br>Writing |

# Troubleshooting

Additional information may be found from the Support page.

**Copyright Information**

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.