Create accounts for FlexPod devices

Converged Systems Advisor

Thom Illingworth, Rachel Lithman
July 28, 2020

This PDF was generated from https://docs.netapp.com/us-en/converged-systems-advisor/task_create_accounts_flexpod_devices.html on March 06, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Create accounts for FlexPod devices . . . 1
- Create a read-only account for Cisco UCS Manager . . . 1
- Create a read-only account for Nexus switches . . . 1
- Create an admin account for ONTAP . . . 2
- Create a read-only account for VMware . . . 2
- Create a read-only account on the APIC . . . 2
- Grant CSA user privileges using a TACACS+ server . . . 3

Create accounts for FlexPod devices

To get started, set up accounts for FlexPod devices:

- Create a read-only account for Cisco UCS Manager
- Create a read-only account for Nexus switches
- Create an admin account for ONTAP
- Create a read-only account for VMware
- Create a read-only account on the APIC
- Grant CSA user privileges using a TACACS+ server

The agent uses these accounts to collect configuration information from each device.

Create a read-only account for Cisco UCS Manager

Steps

1. Log in to Cisco UCS Manager.
2. Create a locally authenticated user named *csa-readonly*.

> All new users are read-only by default.

Create a read-only account for Nexus switches

Steps

1. Log in to each Nexus switch using SSH or Telnet.
2. Enter global configuration mode:

```
 configure terminal
.. Create a new user:
```

```
 username [name] password [password] role network-operator
.. Save the configuration:
```

```
copy running configuration startup configuration
```

If you are using a TACACS+ server and you need to grant CSA user privileges, go to Granting CSA user privileges using a TACACS+ server.

Create an admin account for ONTAP

Steps

1. Log in to OnCommand System Manager and click the settings icon:



2. On the Users page, click **Add**.
3. Enter a user name and password and add **ssh**, **ontapi** and **console** as user login methods with admin access.

Create a read-only account for VMware

Steps

1. Log in to vCenter.
2. In the vCenter menu, choose **Administration**.
3. Under roles, choose **Read-only**.
4. Click the icon for **Clone role action** and change the name to **CSA**.
5. Select the newly created **CSA** role.
6. Click the **Edit role** icon.
7. Under **Edit role**, choose **Global** and then check **Licenses**.
8. On the sidebar, select **Single sign on→Users and groups→Create a new user**.
9. Name the new user **CSARO** under DOMAIN vpshere.local.
10. On the sidebar, select **Global Permissions** under **Access Control**.
11. Choose the user **CSARO** and assign ROLE **CSA**.
12. Log in to the Web Client.

    Use user ID: **CSARO@vsphere.local** and previously created password.

Create a read-only account on the APIC

Steps

1. Click **Admin**.
2. Click **Create new local users**.
3. Under **User Identity**, enter the user information.
4. Under **Security** select all security domain options.
5. Click **+** to add user certificates and SSH keys if needed.

6. Click **Next**.
7. Click **+** to add roles for your domain.
8. Select the **Role Name** from the dropdown menu.
9. Select **Read** for the **Role Privilege Type**.
10. Click **Finish**.

Grant CSA user privileges using a TACACS+ server

If you are using a TACACS+ server and you need to grant CSA user privileges for your switches, you should create a user privilege group and grant the group access to the specific setup commands needed by CSA.

The following commands should be written into the configuration file for your TACACS+ server.

Steps

1. Enter the following to create a user privilege group with read-only access:

```
group=group_name {
  default service=deny
  service=exec{
    priv-lvl=0
  }
}
```

1. Enter the following to grant access to commands needed by CSA:

```
cmd=show {
  permit "environment"
  permit "version"
  permit "feature"
  permit "feature-set"
  permit hardware.*
  permit "interface"
  permit "interface"
  permit "interface transceiver"
  permit "inventory"
  permit "license"
  permit "module"
  permit "port-channel database"
  permit "ntp peers"
  permit "license usage"
  permit "port-channel summary"
  permit "running-config"
  permit "startup-config"
  permit "running-config diff"
  permit "switchname"
  permit "int mgmt0"
  permit "cdp neighbors detail"
  permit "vlan"
  permit "vpc"
  permit "vpc peer-keepalive"
  permit "mac address-table"
  permit "lacp port-channel"
  permit "policy-map"
  permit "policy-map system type qos"
  permit "policy-map system type queuing"
  permit "policy-map system type network-qos"
  permit "zoneset active"
  permit "san-port-channel summary"
  permit "flogi database"
  permit "fcns database detail"
  permit "fcns database detail"
  permit "zoneset active"
  permit "vsan"
  permit "vsan usage"
  permit "vsan membership"
  }
```

1. Enter the following to add your CSA user account to the newly created group:

```
user=user_account{
  member=group_name
  login=file/etc/passwd
}
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.