Cloud Manager 的 AWS 和 Azure 限

Cloud Manager 3.6

Ben Cammett
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/occm36/reference_permissions.html on October 27, 2021. Always check docs.netapp.com for the latest.

目□

Cloud Manager 的 AWS 和 Azure □限 1
Cloud Manager 如何使用 AWS □限 1
Cloud Manager 使用 Azure □限的功能 2

Cloud Manager 的 AWS 和 Azure □限

Cloud Manager 需要□限才能代表□在 AWS 和 Azure 中□行操作。中包括□些□限 "NetApp 提供的策略"。□可能希望了解 Cloud Manager 使用□些□限□行的操作。

Cloud Manager 如何使用 AWS □限

Cloud Manager 使用 AWS □□□几个 AWS 服□□行 API □用、包括 EC2 、 S3 、 Cloudformation 、 IAM 、 Security Token Service （安全令牌服□， STS ）和密□管理服□（ KMS ）。

操作	目的
"EC2 ： StartInstances " ， "EC2 ： StopInstances " ， "EC2 ： Describe Instances " ， "EC2 ： Describe InstanceStatus" ， "EC2 ： RunInstances " ， "EC2 ：□端□例 " ， "EC2 ： ModifyInstanceAttribute" ,	□□ Cloud Volumes ONTAP □例并停止、□□和□控□例。
"EC2 ：描述□例属性 " 、	□□是否已□支持的□例□型□用□□网□。
"EC2 ：描述□ " 、 "EC2 ：描述□ " 、	□□ Cloud Volumes ONTAP HA 配置。
"EC2 ：□建□□ " 、	□□ Cloud Manager 使用 "Workingviron" 和 "Workingvironmid" □□□建的□个□源。Cloud Manager 使用□些□□□行□□和成本分配。
"EC2 ： CreateVolume" ， "EC2 ： Describe Volumes" ， "EC2 ： ModifyVolumeAttribute" ， "EC2 ： AttachVolume" ， "EC2 ： DeleteVolume" ， "EC2 ：□□卷 " ,	管理 Cloud Volumes ONTAP 用作后端存□的 EBS 卷。
"EC2 ： CreateSecurityGroup" ， "EC2 ： DeleteSecurityGroup" ， "EC2 ： Describe SecurityGroups" ， "EC2 ： RevokeSecurityGroupEated" ， "EC2 ： AuthorizeSecurityGroupEated" ， "EC2 ： AuthorizeSecurityGroupIn防□ " ， "EC2 ： RevokeSecurityGroupIn防□ " ,	□ Cloud Volumes ONTAP □建□定□的安全□。
"EC2 ： CreateNetworkInterface" ， "EC2 ： Describe NetworkInterfaces" ， "EC2 ： DeleteNetworkInterface" ， "EC2 ： ModifyNetworkInterfaceAttribute" ,	在目□子网中□ Cloud Volumes ONTAP □建和管理网□接口。
"EC2 ：描述性子网 " 、 "EC2 ：描述性 VPCS" 、	□取目□子网和安全□的列表、在□ Cloud Volumes ONTAP □建新的工作□境□需要□些子网和安全□。
"EC2 ：□明 " 、	□定□□ Cloud Volumes ONTAP □例□的 DNS 服□器和默□域名。
"EC2 ： CreateSnapshot " 、 "EC2 ： DeleteSnapshot " 、 "EC2 ：描述性快照 " 、	在初始□置期□和停止 Cloud Volumes ONTAP □例□拍□ EBS 卷的快照。
"EC2 ： GetConsoleOutput " 、	捕□附加到 AutoSupport 消息的 Cloud Volumes ONTAP 控制台。
"EC2 ：描述性密□□ " 、	在□□□例□□取可用密□□的列表。

操作	目的
"EC2 ：描述性 " 、	□得可用 AWS 区域的列表。
"EC2 ：□除□□ " 、 "EC2 ：描述□□ " 、	管理与 Cloud Volumes ONTAP □例□□的□源□□。
"CloudFormation ： CreateStack" ， "CloudFormation ： DeleteStack" ， "CloudFormation ： Describe Stacks" ， "CloudFormation ： Describe StackEvents " ， "CloudFormation ： ValidateTemplate" ,	□□ Cloud Volumes ONTAP □例。
"IAM ： PassRole" ， "iam ： CreateRole" ， "iam ： DeleteRole" ， "iam ： PutRolePolicy" ， "iam ： CreateInstanceProfile" ， "IAM ： DeleteRolePolicy" ， "iam ： AddRoleToInstanceProfile" ， "iam ： RemoveRoleFromInstanceProfile" ， "iam ： DeleteInstanceProfile" ,	□□ Cloud Volumes ONTAP HA 配置。
"IAM ： ListInstanceProfiles" ， "STS ： DecodeAuthorizationMessage" ， "EC2 ： AssociateIamInstanceProfile" ， "EC2 ： Describe IamInstanceProfileAssociations" ， "EC2 ： DisassociateIamInstanceProfile" ,	管理 Cloud Volumes ONTAP □例的□例配置文件。
"S3 ： GetBucketTagging" ， "S3 ： GetBucketLocation" ， "S3 ： ListAllMyBuckets" , "S3 ： ListBucket"	□取有□ AWS S3 存□槽的信息、以便 Cloud Manager 可以与 NetApp Data Fabric Cloud Sync 服□集成。
"S3 ： CreateBucket" ， "S3 ： DeleteBucket" ， "S3 ： GetLifeycleConfiguration" ， "S3 ： PutLifeycleConfiguration" ， "S3 ： PutBucketTagging" ， "S3 ： ListBucketVersions" ,	管理 Cloud Volumes ONTAP 系□将其用作容量□的 S3 存□区。
"KMS: List*" 、 "KMS: 描述 *"	从 AWS 密□管理服□□取有□密□的信息。
"CE ： GetReservationUtilization" ， "ce ： GetDimensionValues" ， "ce ： GetCostAndUsage" ， "ce ： GetTags "	□取有□ Cloud Volumes ONTAP 的 AWS 成本数据。
"EC2 ： CreatePlacementGroup" ， "EC2 ： DeletePlacementGroup"	在□个 AWS 可用性区域中部署 HA 配置□， Cloud Manager 会□□ AWS 分布式放置□中的□个 HA □点和□解器。

Cloud Manager 使用 Azure □限的功能

Cloud Manager Azure 策略包括 Cloud Manager 在 Azure 中部署和管理 Cloud Volumes ONTAP 所需的□限。

操作	目的
Microsoft.Compute/locations/operations/read" , Microsoft.Compute/locations/vmSizes/read" , Microsoft.Compute/operations/read" , Microsoft.Compute/virtualMachines/instanceView/read" , Microsoft.Compute/virtualMachines/powerOff/action" , Microsoft.Compute/virtualMachines/read" , Microsoft.Compute/virtualMachines/restart/action" , Microsoft.Compute/virtualMachines/start/action" , Microsoft.Compute/virtualMachines/deallocate/action" , Microsoft.Compute/virtualMachines/vmSizes/read" , " Microsoft.Compute/virtualMachines/write" ,	□建 Cloud Volumes ONTAP 并停止、□□、□除和□取系□状□。
"Microsoft.compute/images/write" 、 "Microsoft.compute/images/read" 、	支持从 VHD 部署 Cloud Volumes ONTAP 。
Microsoft.Compute/disks/delete" , Microsoft.Compute/disks/read" , Microsoft.Compute/disks/write" , "microsoft.Storage/SchecknameAvailability /Read" , "microsoft.Storage/operations/Read" , "microsoft.Storage/storageAccounts" , "microsoft.Storage/storageAccouns/Read" , "microsoft.Storage/storageAccounts" , "microsoft.Storage/storageAccounts" , "microsoft.Storage/storageAccounts" , "microsoft.Storage/storageAccounts" , "microsoft.Storage/Acces/ Read" ,	管理 Azure 存□□□和磁□、并将磁□□接到 Cloud Volumes ONTAP 。
"microsoft.network/networkinterfaces/read" 、 "microsoft.network/networkinterfaces/write" 、 "microsoft.network/networkinterfaces/join/action" 、	在目□子网中□ Cloud Volumes ONTAP □建和管理网□接口。
"microsoft.network/networksecuritygroups/read" 、 "microsoft.network/networksecuritygroups/write" 、 "microsoft.network/networksecuritygroups/join/action" 、	□ Cloud Volumes ONTAP □建□定□的网□安全□。
"microsoft.resources/subscriptions/locations/read" , Microsoft.Network/locations/operationResults/read" , Microsoft.Network/locations/operations/read" , Microsoft.Network/virtualNetworks/read" , Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read" , Microsoft.Network/virtualNetworks/subnets/read" , Microsoft.Network/virtualNetworks/subnets/virtualMachines/read" , Microsoft.Network/virtualNetworks/virtualMachines/read" , Microsoft.Network/virtualNetworks/subnets/join/action" ,	□取有□区域、目□ VNet 和子网的网□信息、并将 Cloud Volumes ONTAP 添加到 VNETS 。
Microsoft.Network/virtualNetworks/subnets/write" , Microsoft.Network/routeTables/join/action" ,	□用 VNet 服□端点以□行数据分□。

操作	目的
"Microsoft.Resources/deployments/operations/read" 、 "Microsoft.Resources/deployments/read" 、 "Microsoft.Resources/deployments/write" 、	从模板部署 Cloud Volumes ONTAP 。
"microsoft.resources/deployments/operations/read" , "microsoft.resources/deployments/read" , "microsoft.resources/deployments/write" , "microsoft.resources/resources/read" , "microsoft.resources/subscriptions/operationresults/read" , "microsoft.resources/subscriptions/resourcegroups/delete" , "microsoft.resources/subscriptions/resourcegroups/read" , "microsoft.resources/subscriptions/resourcegroups/write" ,	□ Cloud Volumes ONTAP □建和管理□源□。
"Microsoft.compute/Snapshots/write" 、 "Microsoft.compute/Snapshots/read" 、 "Microsoft.compute/disks/begingetAccess/Action"	□建和管理 Azure 管理的快照。
"microsoft.compute/availabilitysets/write" 、 "microsoft.compute/availabilitysets/read" 、	□建和管理 Cloud Volumes ONTAP 的可用性集。
"Microsoft.Marketplac□□ / 服□□型 / □布者 / 服□ / □□ / □□ / □取 " 、 "Microsoft.Marketplac□□ / 服□□型 / □布者 / 服□ / □□ / □□ / 写入 "	支持从 Azure Marketplace □行□程部署。
Microsoft.Network/loadBalancers/read" , Microsoft.Network/loadBalancers/write" , Microsoft.Network/loadBalancers/delete" , Microsoft.Network/loadBalancers/backendAddressPools/read" , Microsoft.Network/loadBalancers/backendAddressPools/join/action" , Microsoft.Network/loadBalancers/frontendIPConfigurations/read" , Microsoft.Network/loadBalancers/loadBalancingRules/read" , Microsoft.Network/loadBalancers/probes/read" , Microsoft.Network/loadBalancers/probes/join/action" ,	管理 HA □的 Azure □□平衡器。
"Microsoft.Authorization/Locks/*"	支持管理 Azure 磁□上的□定。
"microsoft.Authorization/roleDefinitions/write" , "microsoft.Authorization/roleAssignments/write" , "microsoft.Web/sites/*"	管理 HA □的故障□移。

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.