Data tiering overview

Cloud Manager 3.6

Ben Cammett
June 03, 2019

This PDF was generated from https://docs.netapp.com/us-en/occm36/concept_data_tiering.html on December 04, 2020. Always check docs.netapp.com for the latest.

Table of Contents

Data tiering overview 1
How data tiering works in AWS 1
How data tiering works in Microsoft Azure 2
How data tiering affects capacity limits 3
Volume tiering policies 3
Setting up data tiering 4

Data tiering overview

You can reduce your storage costs by enabling automated tiering of inactive data to low-cost object storage. Active data remains in high-performance SSDs or HDDs (the performance tier), while inactive data is tiered to low-cost object storage (the capacity tier). This enables you to reclaim space on your primary storage and shrink secondary storage.

Cloud Volumes ONTAP supports data tiering in AWS and in Microsoft Azure. Data tiering is powered by FabricPool technology.

> You do not need to install a feature license to enable data tiering.

How data tiering works in AWS

When you enable data tiering in AWS, Cloud Volumes ONTAP uses EBS as a performance tier for hot data and AWS S3 as a capacity tier for inactive data:



Performance tier in AWS

The performance tier can be General Purpose SSDs, Provisioned IOPS SSDs, or Throughput Optimized HDDs.

Capacity tier in AWS

By default, Cloud Volumes ONTAP tiers inactive data to the S3 *Standard* storage class. Standard is ideal for frequently accessed data stored across multiple Availability Zones.

If you do not plan to access the inactive data, you can reduce your storage costs by changing a system's tiering level to one of the following, after you deploy Cloud Volumes ONTAP:

Intelligent Tiering

Optimizes storage costs by moving data between two tiers as data access patterns change. One tier is for frequent access and the other is for infrequent access.

One Zone-Infrequent Access

For infrequently accessed data stored in a single Availability Zone.

Standard-Infrequent Access

For infrequently accessed data stored across multiple Availability Zones.

The access costs are higher if you do access the data, so you must take that into consideration before you change the tiering level. For more details about S3 storage classes, refer to AWS documentation.

When you change the tiering level, inactive data starts in the Standard storage class and moves to the storage class that you selected, if the data is not accessed after 30 days. For details about changing the tiering level, see Tiering inactive data to low-cost object storage.

The tiering level is system wide—it is not per volume.

A Cloud Volumes ONTAP working environment uses an S3 bucket for all tiered data from the system. A different S3 bucket is not used for each volume. This includes an HA working environment. Cloud Manager creates an S3 bucket and names it fabric-pool-*cluster unique identifier*.

How data tiering works in Microsoft Azure

When you enable data tiering in Azure, Cloud Volumes ONTAP uses Azure managed disks as a performance tier for hot data and Azure Blob storage as a capacity tier for inactive data:



Performance tier in Azure

The performance tier can be either Premium Storage (SSD) or Standard Storage (HDD).

Capacity tier in Azure

By default, Cloud Volumes ONTAP tiers inactive data to the Azure *hot* storage tier, which is ideal for frequently accessed data.

If you do not plan to access the inactive data, you can reduce your storage costs by changing a system's tiering level to the Azure *cool* storage tier after you deploy Cloud Volumes ONTAP. The cool tier is ideal for infrequently accessed data that will reside in the tier for at least 30 days.

The access costs are higher if you do access the data, so you must take that into consideration before you change the tiering level. For more details about Azure Blob storage tiers, refer to Azure documentation.

When you change the tiering level, inactive data starts in the hot storage tier and moves to the cool storage tier, if the data is not accessed after 30 days. For details about changing the tiering level, see Tiering inactive data to low-cost object storage.

The tiering level is system wide—it is not per volume.

> A Cloud Volumes ONTAP working environment uses an Azure Blob container for all tiered data from the system. A different container is not used for each volume. Cloud Manager creates a new storage account with a container for each Cloud Volumes ONTAP system. The name of the storage account is random.

How data tiering affects capacity limits

If you enable data tiering, a system's capacity limit stays the same. The limit is spread across the performance tier and the capacity tier.

Volume tiering policies

To enable data tiering, you must select a volume tiering policy when you create, modify, or replicate a volume. You can select a different policy for each volume.

Some tiering policies have an associated minimum cooling period, which sets the time that user data in a volume must remain inactive for the data to be considered "cold" and moved to the capacity tier.

Cloud Volumes ONTAP supports the following tiering policies:

Snapshot Only

After an aggregate has reached 50% capacity, Cloud Volumes ONTAP tiers cold user data of Snapshot copies that are not associated with the active file system to the capacity tier. The cooling period is approximately 2 days.

If read, cold data blocks on the capacity tier become hot and are moved to the performance tier.

Auto

After an aggregate has reached 50% capacity, Cloud Volumes ONTAP tiers cold data blocks in a volume to a capacity tier. The cold data includes not just Snapshot copies but also cold user data from the active file system. The cooling period is approximately 31 days.

This policy is supported starting with Cloud Volumes ONTAP 9.4.

If read by random reads, the cold data blocks in the capacity tier become hot and move to the performance tier. If read by sequential reads, such as those associated with index and antivirus scans, the cold data blocks stay cold and do not move to the performance tier.

Backup

When you replicate a volume for disaster recovery or long-term retention, data for the destination volume starts in the capacity tier. If you activate the destination volume, the data gradually moves to the performance tier as it is read.

None

Keeps data of a volume in the performance tier, preventing it from being moved to the capacity tier.

Setting up data tiering

For instructions and a list of supported configurations, see Tiering inactive data to low-cost object storage.

Copyright Information

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.