Azure 中的高可用性

Cloud Manager 3.7

Ben Cammett
August 09, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/occm37/concept_ha_azure.html on October 27, 2021. Always check docs.netapp.com for the latest.

目□

Azure 中的高可用性□ 1
HA □件 1
RPO 和 RTO 3
存□接管和恢□ 3
存□配置 3
HA 限制 3

Azure 中的高可用性□

Cloud Volumes ONTAP 高可用性（ High Availability， HA ）□可在云□境□生故障□提供企□□可□性和持□□行。在 Azure 中，存□在□个□点之□共享。

HA □件

Azure 中的 Cloud Volumes ONTAP HA 配置包括以下□件：



□注意以下有□ Cloud Manager □□部署的 Azure □件的信息：

Azure □准□□平衡器

□□平衡器管理□入 Cloud Volumes ONTAP HA □的流量。

可用性集

可用性集可□保□点位于不同的故障域和更新域中。

Disks

- □个用于□□卷的 90 GB 高□ SSD 磁□（□个□点一个）
- 根卷的□个 140 GB 高□存□□面 Blobs （□个□点一个）
- □个 128 GB □准 HDD 磁□，用于□省核心（□个□点一个）

存□□□

- 受管磁□需要一个存□□□。
- 高□存□□面 Blobs 需要一个或多个存□□□，因□已□到□个存□□□的磁□容量限制。

  "Azure 文□：存□□□的 Azure 存□可□展性和性能目□"。

- 要将数据分□到 Azure Blob 存□，需要一个存□□□。

RPO 和 RTO

HA 配置可保持数据的高可用性，如下所示：

- 恢□点目□（ RPO ）□ 0 秒。□的数据在□□□程中不会□失数据。
- 恢□□□目□（ RTO ）□ 60 秒。如果□生中断、数据□在 60 秒或更短的□□内可用。

存□接管和恢□

与物理 ONTAP 集群□似， Azure HA □中的存□在□点之□共享。通□□接到配□□点的存□，可以使□个□点在□生 *takeover* □□□□一个□点的存□。网□路径故障□移机制可□保客□端和主机□□与正常□行的□点□行通信。当□点恢□□机□，配□□点 *gives back* storage 。

□于 NAS 配置，如果□生故障，数据 IP 地址会自□在 HA □点之□□移。

□于 iSCSI 、 Cloud Volumes ONTAP 使用多路径 I/O （ MPIO ）和非□称□□□元□□（ ALUA ）来管理活□□化路径和非□化路径之□的路径故障□移。

> 有□□些特定主机配置支持 ALUA 的信息，□参□ "NetApp 互操作性表工具" 以及□用于□的主机操作系□的《 Host Utilities 安装和□置指南》。

存□配置

□可以将 HA □用作主□ - 主□配置、□个□点都将数据提供□客□端、也可以用作主□ - 被□配置、□当被□□点接管了主□□点的存□□才□□数据□求。

HA 限制

以下限制会影□ Azure 中的 Cloud Volumes ONTAP HA □：

- Cloud Volumes ONTAP □准版，高□版和 BYOL 支持 HA □。不支持□□。
- 不支持 NFSv4 。支持 NFSv3 。

- 某些地区不支持 HA □。

  "□参□支持的 Azure 区域列表"。

"了解如何在 Azure 中部署 HA 系□"。

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.