Installing Cloud Manager on an existing Linux host

Cloud Manager 3.7

Ben Cammett
January 08, 2020

This PDF was generated from https://docs.netapp.com/us-en/occm37/task_installing_linux.html on April 22, 2020.
Always check docs.netapp.com for the latest.

Table of Contents

Installing Cloud Manager on an existing Linux host 1

Installing Cloud Manager on an existing Linux host

The most common way to deploy Cloud Manager is from Cloud Central or from a cloud provider's marketplace. But you have the option to download and install the Cloud Manager software on an existing Linux host in your network or in the cloud.

> You can install Cloud Manager on your own host in GCP, but not in your on-premises network. Cloud Manager must be installed in GCP in order to deploy Cloud Volumes ONTAP in GCP.

Before you begin

- A Red Hat Enterprise Linux system must be registered with Red Hat Subscription Management. If it is not registered, the system cannot access repositories to update required 3rd party software during Cloud Manager installation.
- The Cloud Manager installer accesses several URLs during the installation process. You must ensure that outbound internet access is allowed to those endpoints. Refer to Networking requirements for Cloud Manager.

About this task

- Root privileges are not required to install Cloud Manager.
- Cloud Manager installs the AWS command line tools (awscli) to enable recovery procedures from NetApp support.

  If you receive a message that installing the awscli failed, you can safely ignore the message. Cloud Manager can operate successfully without the tools.

- The installer that is available on the NetApp Support Site might be an earlier version. After installation, Cloud Manager automatically updates itself if a new version is available.

Steps

1. Review networking requirements:
   - Networking requirements for Cloud Manager
   - Networking requirements for Cloud Volumes ONTAP in AWS
   - Networking requirements for Cloud Volumes ONTAP in Azure
   - Networking requirements for Cloud Volumes ONTAP in GCP
2. Review Cloud Manager host requirements.
3. Download the software from the NetApp Support Site, and then copy it to the Linux host.

   For help with connecting and copying the file to an EC2 instance in AWS, see AWS Documentation:

Connecting to Your Linux Instance Using SSH.

4. Assign permissions to execute the script.

   Example

   ```
   chmod +x OnCommandCloudManager-V3.7.0.sh
   ```

5. Run the installation script:

   ```
   ./OnCommandCloudManager-V3.7.0.sh [silent] [proxy=ipaddress] [proxyport=port]
   [proxyuser=user_name] [proxypwd=password]
   ```

   silent runs the installation without prompting you for information.

   proxy is required if the Cloud Manager host is behind a proxy server.

   proxyport is the port for the proxy server.

   proxyuser is the user name for the proxy server, if basic authentication is required.

   proxypwd is the password for the user name that you specified.

6. Unless you specified the silent parameter, type **Y** to continue the script, and then enter the HTTP and HTTPS ports when prompted.

   If you change the HTTP and HTTPS ports, you must ensure that users can access the Cloud Manager web console from a remote host:

   - Modify the security group to allow inbound connections through the ports.
   - Specify the port when you enter the URL to the Cloud Manager web console.

     Cloud Manager is now installed. At the end of the installation, the Cloud Manager service (occm) restarts twice if you specified a proxy server.

7. Open a web browser and enter the following URL:

   https://*ipaddress*:*port*

   ipaddress can be localhost, a private IP address, or a public IP address, depending on the configuration of the Cloud Manager host. For example, if Cloud Manager is in the public cloud without a public IP address, you must enter a private IP address from a host that has a connection to the Cloud Manager host.

   port is required if you changed the default HTTP (80) or HTTPS (443) ports. For example, if the HTTPS port was changed to 8443, you would enter https://*ipaddress*:8443

8. Sign up at NetApp Cloud Central or log in.
9. After you log in, set up Cloud Manager:
   a. Specify the Cloud Central account to associate with this Cloud Manager system.

      Learn about Cloud Central accounts.

   b. Enter a name for the system.



After you finish

Set up permissions so Cloud Manager can deploy Cloud Volumes ONTAP in your cloud provider:

- AWS: Set up an AWS account and then add it to Cloud Manager.
- Azure: Set up an Azure account and then add it to Cloud Manager.
- GCP: Set up a service account that has the permissions that Cloud Manager needs to create and manage Cloud Volumes ONTAP systems in projects.
  1. Create a role in GCP that includes the permissions defined in the Cloud Manager policy for GCP.
  2. Create a GCP service account and apply the custom role that you just created.
  3. Associate this service account with the Cloud Manager VM.

4. If you want to deploy Cloud Volumes ONTAP in other projects, grant access by adding the service account with the Cloud Manager role to that project. You'll need to repeat this step for each project.

Copyright Information

Copyright © 2019–2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.