Provision volumes for file services

Cloud Manager 3.7

NetApp
March 25, 2024

This PDF was generated from https://docs.netapp.com/us-en/occm37/task_manage_anf.html on March 25, 2024. Always check docs.netapp.com for the latest.

Table of Contents

Provision volumes for file services . . . 1
Managing volumes for Azure NetApp Files . . . 1
Managing Cloud Volumes Service for AWS . . . 4

Provision volumes for file services

Managing volumes for Azure NetApp Files

View and create NFS volumes for Azure NetApp Files directly from Cloud Manager.

Setting up your configuration

Your configuration needs to meet a few requirements before you can manage volumes for Azure NetApp Files from Cloud Manager.

1. Azure NetApp Files must be set up by completing the following from the Azure portal:
   - Register for Azure NetApp Files
   - Create a NetApp account
   - Set up a capacity pool
   - Delegate a subnet to Azure NetApp Files
2. Cloud Manager must be set up as follows:
   - Cloud Manager must be running in Azure, in the account where Azure NetApp Files was set up.
   - The Cloud Manager virtual machine must receive permissions through a managed identity.

     If you deployed Cloud Manager from Cloud Central, then you're all set. Cloud Central automatically enables a system-assigned managed identity on the Cloud Manager virtual machine.

     If you deployed Cloud Manager from the Azure Marketplace, then you should have followed instructions to enable a managed identity.

   - The Azure role assigned to the Cloud Manager virtual machine must include the permissions listed in the latest Cloud Manager policy for Azure:

     ```
     "Microsoft.NetApp/netAppAccounts/read",
     "Microsoft.NetApp/netAppAccounts/capacityPools/read",
     "Microsoft.NetApp/netAppAccounts/capacityPools/volumes/write",
     "Microsoft.NetApp/netAppAccounts/capacityPools/volumes/read",
     "Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete"
     ```

When your configuration is set up, Cloud Manager automatically displays Azure NetApp Files on the Working Environments page:

Creating volumes

Cloud Manager enables you to create NFSv3 volumes for Azure NetApp Files.

Steps

1. Open the working environment.
2. Click **Add New Volume**.
3. Enter basic details about the volume in the **Account Information** page:
   a. Select an Azure subscription and Azure NetApp Files account.
   b. Enter a name for the volume.
   c. Select a capacity pool and specify a quota, which is the amount of logical storage that's allocated to the volume.



4. Fill out the **Location & Export Policy** page:
   a. Select a VNet and subnet.
   b. Configure an export policy to control access to the volume.



5. Click **Go**.

Getting a volume's mount path

Copy the mount path for a volume so you can mount the volume to a Linux machine.

Steps

1. Open the working environment.
2. Hover over the volume and click the menu.



3. Click **Mount Command**.



4. Copy the mount path and use the copied text to mount the volume to a Linux machine.

Deleting volumes

Delete the volumes that you no longer need.

Steps

1. Open the working environment.

2. Hover over the volume and click the menu.



3. Click **Delete**.
4. Confirm that you want to delete the volume.

Getting help

Use the Cloud Manager chat for general service questions.

For technical support issues associated with Azure NetApp Files, use the Azure portal to log a support request to Microsoft. Select your associated Microsoft subscription and select the **Azure NetApp Files** service name under **Storage.** Provide the remaining information required to create your Microsoft support request.

Cloud Manager provides a local AutoSupport download under the **Support Dashboard** menu option. This 7z file contains an Azure debug file to show inbound and outbound communication to your Azure NetApp Files account.

Limitations

- Cloud Manager doesn’t support SMB volumes.
- Cloud Manager doesn’t enable you to manage capacity pools or volume snapshots.
- You can create volumes with an initial size and single export policy. Editing a volume must be done from the Azure NetApp Files interface in the Azure portal.
- Cloud Manager doesn’t support data replication to or from Azure NetApp Files.

Related links

- NetApp Cloud Central: Azure NetApp Files
- Azure NetApp Files documentation

Managing Cloud Volumes Service for AWS

Cloud Manager enables you to discover the NFS cloud volumes in your Cloud Volumes

Service for AWS subscription. After discovery, you can add additional NFS cloud volumes directly from Cloud Manager.

> Cloud Manager does not support SMB or dual-protocol volumes with Cloud Volumes Service for AWS.

Before you get started

- Cloud Manager enables discovery of *existing* Cloud Volumes Service for AWS subscriptions. See the NetApp Cloud Volumes Service for AWS Account Setup Guide if you haven't set up your subscription yet.

  You must follow this setup process for each region and provision your first volume from Cloud Volumes Service before you can discover the region in Cloud Manager.

- You need to obtain the Cloud Volumes API key and secret key so you can provide them to Cloud Manager. For instructions, refer to Cloud Volumes Service for AWS documentation.

Discovering your Cloud Volumes Service for AWS subscription

To get started, you need to discover the cloud volumes in an AWS region. You can discover additional regions later.

Steps

1. On the Working Environments page, click **Discover**.
2. Select **Cloud Volumes Service for AWS**.
3. Provide information about your Cloud Volumes Service subscription:
   a. Select the AWS region where your cloud volumes reside.
   b. Enter the Cloud Volumes API key and secret key. For instructions, refer to Cloud Volumes Service for AWS documentation.
   c. Click **Go**.

Result

Cloud Manager should now display your Cloud Volumes Service for AWS configuration on the Working Environments page.

Discovering additional regions

If you have cloud volumes in additional regions, you need to discover each individual region.

Steps

1. On the Working Environments page, select the working environment (but don't open it by double-clicking).
2. In the right pane, click **Discover Cloud Volumes Service in another region**.

3. Provide information about your Cloud Volumes Service subscription:
   a. Select the AWS region where your cloud volumes reside.
   b. Enter the Cloud Volumes API key and secret key. For instructions, refer to Cloud Volumes Service for AWS documentation.
   c. Click **Go**.

Result

Cloud Manager discovers information about the cloud volumes in the selected region.

Creating cloud volumes

Cloud Manager enables you to create NFSv3 cloud volumes. You can only create cloud volumes with an initial size and single export policy. Editing the volume must be done from the Cloud Volume Service user interface.

1. Open the working environment.
2. Click **Add New Volume**.
3. Enter details about the volume:
   a. Enter a name for the volume.
   b. Specify a size within the range of 100 GiB to 90,000 GiB (equivalent to 88 TiBs).

      Cloud Manager displays volumes in GiB, while the Cloud Volumes Service displays volumes in GB.

   c. Specify a service level: Standard, Premium, or Extreme.

      Learn more about these service levels.

   d. Choose a region. You can create the volume in a region that Cloud Manager has discovered.
   e. Restrict client access by specifying an IP address or Classless Inter-Domain Routing (CIDR).



4. Click **Go**.

Deleting cloud volumes

Delete the cloud volumes that you no longer need.

Steps

1. Open the working environment.
2. Hover over the volume and click the menu. Click **Delete**.

3. Confirm that you want to delete the volume.

Getting help

Use the Cloud Manager chat for general service questions.

For technical support issues associated with your cloud volumes, use your 20 digit “930” serial number located in the "Support" tab of the Cloud Volumes Service user interface. Use this support ID when opening a web ticket or calling for support. Be sure to activate your Cloud Volumes Service serial number for support from the Cloud Volumes Service user interface. Those steps are explained here.

Limitations

- Cloud Manager does not support SMB or dual-protocol volumes.
- You can only create cloud volumes with an initial size and single export policy. Editing the volume must be done from the Cloud Volume Service user interface.
- Cloud Manager doesn’t support data replication to or from a Cloud Volumes Service for AWS subscription.
- Removing your Cloud Volumes Service for AWS subscription from Cloud Manager isn’t supported. There are no charges to discover a region from Cloud Manager.

Related links

- NetApp Cloud Central: Cloud Volumes Service for AWS
- NetApp Cloud Volumes Service for AWS documentation

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.