多个 AZs 中的 HA 置 AWS 网

Cloud Manager 3.8

Ben Cammett
August 12, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/occm38/task_setting_up_transit_gateway.html on October 27, 2021. Always check docs.netapp.com for the latest.

目□

□多个 AZs 中的 HA □□置 AWS □□网□ 1

□多个 AZs 中的 HA □□置 AWS □□网□

□置 AWS □□网□以允□□□ HA □ "浮□ IP 地址" 从 HA □所在的 VPC 外部。

如果 Cloud Volumes ONTAP HA 配置分布在多个 AWS 可用性区域中，□从 VPC 内部□□ NAS 数据需要浮□ IP 地址。□些浮□ IP 地址可以在□生故障□在□点之□□移，但无法从 VPC 外部本机□□。独立的□用 IP 地址可从 VPC 外部提供数据□□，但不提供自□故障□移。

集群管理接口和可□ SVM 管理 LIF 也需要浮□ IP 地址。

如果□□置了 AWS □□网□，□可以从 HA □所在的 VPC 外部□□浮□ IP 地址。□意味着 VPC 外部的 NAS 客□端和 NetApp 管理工具可以□□浮□ IP 。

以下示例□示了通□□□网□□接的□个 vPC 。一个 HA 系□□留在一个 VPC 中，而一个客□端□留在□一个 VPC 中。然后，□可以使用浮□ IP 地址在客□端上挂□ NAS 卷。



以下□□□明了如何□置□似的配置。

□□

1. "□建□□网□并将 vPC □接到□网□"。
2. 通□指定 HA □的浮□ IP 地址，在□□网□的路由表中□建路由。

   □可以在 Cloud Manager 的 " 工作□境信息 " □面上□到浮□ IP 地址。以下是一个示例：



   下□示例□示了□□网□的路由表。它包括到 Cloud Volumes ONTAP 所使用的□个 vPC 的 CIDR □和四个浮□ IP 地址的路由。

3. 修改需要□□浮□ IP 地址的 vPC 的路由表。

   a. 向浮□ IP 地址添加路由条目。
   b. 向 HA □所在 VPC 的 CIDR □添加路由条目。

      下□示例□示了 VPC 2 的路由表，其中包括指向 VPC 1 的路由和浮□ IP 地址。



4. 通□向需要□□浮□ IP 地址的 VPC 添加路由来修改 HA □的 VPC 的路由表。

   此□□非常重要，因□它会完成 VPC 之□的路由。

   下□示例□示了 VPC 1 的路由表。它包括一条指向浮□ IP 地址和客□端所在 VPC 2 的路由。Cloud Manager 在部署 HA □□会自□将浮□ IP 添加到路由表中。



5. 使用浮□ IP 地址将卷挂□到客□端。

   通□□□卷并□□ * 挂□命令 * ， □可以在 Cloud Manager 中□到正□的 IP 地址。



- 相□□接 *
- "AWS 中的高可用性□"
- "AWS 中的 Cloud Volumes ONTAP 的网□要求"

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.