AWS

Cloud Manager 3.8

NetApp
March 25, 2024

This PDF was generated from https://docs.netapp.com/us-en/occm38/concept_accounts_aws.html on March 25, 2024. Always check docs.netapp.com for the latest.

Table of Contents

AWS 1
AWS credentials and permissions 1
Managing AWS credentials and subscriptions for Cloud Manager 3

AWS

AWS credentials and permissions

Cloud Manager enables you to choose the AWS credentials to use when deploying Cloud Volumes ONTAP. You can deploy all of your Cloud Volumes ONTAP systems using the initial AWS credentials, or you can add additional credentials.

Initial AWS credentials

When you deploy a Connector from Cloud Manager, you need to use an AWS account that has permissions to launch the Connector instance. The required permissions are listed in the Connector deployment policy for AWS.

When Cloud Manager launches the Connector instance in AWS, it creates an IAM role and an instance profile for the instance. It also attaches a policy that provides Cloud Manager with permissions to manage resources and processes within that AWS account. Review how Cloud Manager uses the permissions.



Cloud Manager selects these AWS credentials by default when you create a new working environment for Cloud Volumes ONTAP:



Additional AWS credentials

If you want to launch Cloud Volumes ONTAP in different AWS accounts, then you can either provide AWS keys for an IAM user or the ARN of a role in a trusted account. The following image shows two additional accounts, one providing permissions through an IAM role in a trusted account and another through the AWS keys of an IAM user:



You would then add the account credentials to Cloud Manager by specifying the Amazon Resource Name (ARN) of the IAM role, or the AWS keys for the IAM user.

After you add another set of credentials, you can switch to them when creating a new working environment:



What about Marketplace deployments and on-prem deployments?

The sections above describe the recommended deployment method for the Connector, which is from Cloud Manager. You can also deploy a Connector in AWS from the AWS Marketplace and you can install the Connector on-premises.

If you use the Marketplace, permissions are provided in the same way. You just need to manually create and set up the IAM role, and then provide permissions for any additional accounts.

For on-premises deployments, you can't set up an IAM role for the Cloud Manager system, but you can provide permissions just like you would for additional AWS accounts.

How can I securely rotate my AWS credentials?

As described above, Cloud Manager enables you to provide AWS credentials in a few ways: an IAM role associated with the Connector instance, by assuming an IAM role in a trusted account, or by providing AWS access keys.

With the first two options, Cloud Manager uses the AWS Security Token Service to obtain temporary credentials that rotate constantly. This process is the best practice—it's automatic and it's secure.

If you provide Cloud Manager with AWS access keys, you should rotate the keys by updating them in Cloud Manager at a regular interval. This is a completely manual process.

Managing AWS credentials and subscriptions for Cloud Manager

When you create a Cloud Volumes ONTAP system, you need to select the AWS credentials and subscription to use with that system. If you manage multiple AWS subscriptions, you can assign each one of them to different AWS credentials from the Credentials page.

Before you add AWS credentials to Cloud Manager, you need to provide the required permissions to that account. The permissions enable Cloud Manager to manage resources and processes within that AWS account. How you provide the permissions depends on whether you want to provide Cloud Manager with AWS keys or the ARN of a role in a trusted account.

> When you deployed a Connector from Cloud Manager, Cloud Manager automatically added AWS credentials for the account in which you deployed the Connector. This initial account is not added if you manually installed the Connector software on an existing system. Learn about AWS credentials and permissions.

Choices

- Granting permissions by providing AWS keys
- Granting permissions by assuming IAM roles in other accounts

How can I securely rotate my AWS credentials?

Cloud Manager enables you to provide AWS credentials in a few ways: an IAM role associated with the Connector instance, by assuming an IAM role in a trusted account, or by providing AWS access keys. Learn more about AWS credentials and permissions.

With the first two options, Cloud Manager uses the AWS Security Token Service to obtain temporary credentials that rotate constantly. This process is the best practice, it's automatic and it's secure.

If you provide Cloud Manager with AWS access keys, you should rotate the keys by updating them in Cloud Manager at a regular interval. This is a completely manual process.

Granting permissions by providing AWS keys

If you want to provide Cloud Manager with AWS keys for an IAM user, then you need to grant the required permissions to that user. The Cloud Manager IAM policy defines the AWS actions and resources that Cloud Manager is allowed to use.

Steps

1. Download the Cloud Manager IAM policy from the Cloud Manager Policies page.
2. From the IAM console, create your own policy by copying and pasting the text from the Cloud Manager IAM policy.

   AWS Documentation: Creating IAM Policies

3. Attach the policy to an IAM role or an IAM user.
   - AWS Documentation: Creating IAM Roles
   - AWS Documentation: Adding and Removing IAM Policies

Result

The account now has the required permissions. You can now add it to Cloud Manager.

Granting permissions by assuming IAM roles in other accounts

You can set up a trust relationship between the source AWS account in which you deployed the Connector instance and other AWS accounts by using IAM roles. You would then provide Cloud Manager with the ARN of the IAM roles from the trusted accounts.

Steps

1. Go to the target account where you want to deploy Cloud Volumes ONTAP and create an IAM role by selecting **Another AWS account**.

   Be sure to do the following:

   - Enter the ID of the account where the Connector instance resides.
   - Attach the Cloud Manager IAM policy, which is available from the Cloud Manager Policies page.

2. Go to the source account where the Connector instance resides and select the IAM role that is attached to

the instance.

a. Click **Attach policies** and then click **Create policy**.

b. Create a policy that includes the "sts:AssumeRole" action and the ARN of the role that you created in the target account.

Example

```
{
 "Version": "2012-10-17",
 "Statement": {
   "Effect": "Allow",
   "Action": "sts:AssumeRole",
   "Resource": "arn:aws:iam::ACCOUNT-B-ID:role/ACCOUNT-B-ROLENAME"
}
}
```

Result

The account now has the required permissions. You can now add it to Cloud Manager.

Adding AWS credentials to Cloud Manager

After you provide an AWS account with the required permissions, you can add the credentials for that account to Cloud Manager. This enables you to launch Cloud Volumes ONTAP systems in that account.

Steps

1. In the upper right of the Cloud Manager console, click the Settings icon, and select **Credentials**.



2. Click **Add Credentials** and select **AWS**.
3. Provide AWS keys or the ARN of a trusted IAM role.
4. Confirm that the policy requirements have been met and click **Continue**.
5. Choose the pay-as-you-go subscription that you want to associate with the credentials, or click **Add Subscription** if you don't have one yet.

   To create a pay-as-you-go Cloud Volumes ONTAP system, AWS credentials must be associated with a subscription to Cloud Volumes ONTAP from the AWS Marketplace.

6. Click **Add**.

Result

You can now switch to a different set of credentials from the Details and Credentials page when creating a new working environment:



Associating an AWS subscription to credentials

After you add your AWS credentials to Cloud Manager, you can associate an AWS Marketplace subscription with those credentials. The subscription enables you to create a pay-as-you-go Cloud Volumes ONTAP system, and to use other NetApp cloud services.

There are two scenarios in which you might associate an AWS Marketplace subscription after you've already added the credentials to Cloud Manager:

- You didn't associate a subscription when you initially added the credentials to Cloud Manager.
- You want to replace an existing AWS Marketplace subscription with a new subscription.

What you'll need

You need to create a Connector before you can change Cloud Manager settings. Learn how.

Steps

1. In the upper right of the Cloud Manager console, click the Settings icon, and select **Credentials**.
2. Hover over a set of credentials and click the action menu.
3. From the menu, click **Associate Subscription**.



4. Select a subscription from the down-down list or click **Add Subscription** and follow the steps to create a new subscription.

   ► https://docs.netapp.com/us-en/occm38//media/video_subscribing_aws.mp4 *(video)*

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.