GCP

Cloud Manager 3.8

NetApp
March 25, 2024

This PDF was generated from https://docs.netapp.com/us-en/occm38/concept_accounts_gcp.html on March 25, 2024. Always check docs.netapp.com for the latest.

Table of Contents

GCP 1
Google Cloud projects, permissions, and accounts 1
Managing GCP credentials and subscriptions for Cloud Manager 2

GCP

Google Cloud projects, permissions, and accounts

A service account provides Cloud Manager with permissions to deploy and manage Cloud Volumes ONTAP systems in the same project as Cloud Manager, or in different projects.

Project and permissions for Cloud Manager

Before you can deploy Cloud Volumes ONTAP in Google Cloud, you must first deploy a Connector in a Google Cloud project. The Connector can't be running on your premises, or in a different cloud provider.

Two sets of permissions must be in place before you deploy a Connector directly from Cloud Manager:

1. You need to deploy a Connector using a Google account that has permissions to launch the Connector VM instance from Cloud Manager.
2. When deploying the Connector, you are prompted to select a service account for the VM instance. Cloud Manager gets permissions from the service account to create and manage Cloud Volumes ONTAP systems on your behalf. Permissions are provided by attaching a custom role to the service account.

We have set up two YAML files that include the required permissions for the user and the service account. Learn how to use the YAML files to set up permissions.

The following image depicts the permission requirements described in numbers 1 and 2 above:



Project for Cloud Volumes ONTAP

Cloud Volumes ONTAP can reside in the same project as the Connector, or in a different project. To deploy Cloud Volumes ONTAP in a different project, you need to first add the Connector service account and role to that project.

- Learn how to set up service account (see step 2).
- Learn how to deploy Cloud Volumes ONTAP in GCP and select a project.

Account for data tiering

> Cloud Manager requires a GCP account for Cloud Volumes ONTAP 9.6, but not for 9.7 and later. If you want to use data tiering with Cloud Volumes ONTAP 9.7, then follow step 4 in Getting started with Cloud Volumes ONTAP in Google Cloud Platform.

Adding a Google Cloud account to Cloud Manager is required to enable data tiering on a Cloud Volumes ONTAP 9.6 system. Data tiering automatically tiers cold data to low-cost object storage, enabling you to reclaim space on your primary storage and shrink secondary storage.

When you add the account, you need to provide Cloud Manager with a storage access key for a service account that has Storage Admin permissions. Cloud Manager uses the access keys to set up and manage a Cloud Storage bucket for data tiering.

After you add a Google Cloud account, you can then enable data tiering on individual volumes when you create, modify, or replicate them.

- Learn how to set up and add GCP accounts to Cloud Manager.
- Learn how to tier inactive data to low-cost object storage.

Managing GCP credentials and subscriptions for Cloud Manager

You can manage two types of Google Cloud Platform credentials from Cloud Manager: the credentials that are associated with the Connector VM instance and storage access keys used with a Cloud Volumes ONTAP 9.6 system for data tiering.

Associating a Marketplace subscription with GCP credentials

When you deploy a Connector in GCP, Cloud Manager creates a default set of credentials that are associated with the Connector VM instance. These are the credentials that Cloud Manager uses to deploy Cloud Volumes ONTAP.

At any time, you can change the Marketplace subscription that's associated with these credentials. The subscription enables you to create a pay-as-you-go Cloud Volumes ONTAP system, and to use other NetApp cloud services.

Steps

1. In the upper right of the Cloud Manager console, click the Settings icon, and select **Credentials**.
2. Hover over a set of credentials and click the action menu.
3. From the menu, click **Associate Subscription**.



4. Select a Google Cloud project and subscription from the down-down list or click **Add Subscription** and follow the steps to create a new subscription.



5. Click **Associate**.

Setting up and adding GCP accounts for data tiering with Cloud Volumes ONTAP 9.6

If you want to enable a Cloud Volumes ONTAP 9.6 system for data tiering, you need to provide Cloud Manager with a storage access key for a service account that has Storage Admin permissions. Cloud Manager uses the access keys to set up and manage a Cloud Storage bucket for data tiering.

> If you want to use data tiering with Cloud Volumes ONTAP 9.7, then follow step 4 in Getting started with Cloud Volumes ONTAP in Google Cloud Platform.

Setting up a service account and access keys for Google Cloud Storage

A service account enables Cloud Manager to authenticate and access Cloud Storage buckets used for data tiering. The keys are required so that Google Cloud Storage knows who is making the request.

Steps

1. Open the GCP IAM console and create a service account that has the Storage Admin role.



2. Go to GCP Storage Settings.
3. If you're prompted, select a project.
4. Click the **Interoperability** tab.
5. If you haven't already done so, click **Enable interoperability access**.
6. Under **Access keys for service accounts**, click **Create a key for a service account**.
7. Select the service account that you created in step 1.



8. Click **Create Key**.

9. Copy the access key and secret.

   You'll need to enter this information in Cloud Manager when you add the GCP account for data tiering.

Adding a GCP account to Cloud Manager

Now that you have an access key for a service account, you can add it to Cloud Manager.

What you'll need

You need to create a Connector before you can change Cloud Manager settings. Learn how.

Steps

1. In the upper right of the Cloud Manager console, click the Settings icon, and select **Credentials**.



2. Click **Add Credentials** and select **Google Cloud**.
3. Enter the access key and secret for the service account.

   The keys enable Cloud Manager to set up a Cloud Storage bucket for data tiering.

4. Confirm that the policy requirements have been met and then click **Create Account**.

What's next?

You can now enable data tiering on individual volumes on a Cloud Volumes ONTAP 9.6 system when you create, modify, or replicate them. For details, see Tiering inactive data to low-cost object storage.

But before you do, be sure that the subnet in which Cloud Volumes ONTAP resides is configured for Private Google Access. For instructions, refer to Google Cloud Documentation: Configuring Private Google Access.

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.