在Linux上安裝或解除安裝7-Mode Transition Tool（僅限複製型轉換）

ONTAP 7-Mode Transition

NetApp
May 03, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/ontap-7mode-transition/install-admin/concept_system_requirements_for_7_mode_transition_tool_on_linux.html on May 03, 2022.
Always check docs.netapp.com for the latest.

目錄

在Linux上安裝或解除安裝7-Mode Transition Tool（僅限複製型轉換） 1
在Linux上安裝7-Mode Transition Tool的系統需求 1
在Linux上安裝7-Mode Transition Tool 1
在Linux上解除安裝7-Mode Transition Tool 2

在Linux上安裝或解除安裝7-Mode Transition Tool（僅限複製型轉換）

您可以使用命令列介面、在Linux系統上下載並安裝7-Mode Transition Tool。必要時、您可以解除安裝7-Mode Transition Tool。

您只能在Linux系統上執行複本型轉換。Linux不支援無複製轉換。

> Linux不支援7-Mode Transition Tool網路介面。您必須使用CLI在Linux系統上執行複本型轉換工作。

在Linux上安裝7-Mode Transition Tool的系統需求

您必須確保Linux主機具備安裝及執行7-Mode Transition Tool所需的組態。

請務必參閱目前的7-Mode Transition Tool "版本資訊" 以取得支援主機和已知問題的最新資訊。

硬體需求

- 雙核心x64處理器、1.0 GHz以上
- 8 GB RAM
- 40 GB可用磁碟空間

軟體需求

- 您的Linux系統必須執行下列其中一項：
  - Red Hat Enterprise Linux 5.6
  - Red Hat Enterprise Linux 6.0
  - Red Hat Enterprise Linux 7.0（7-Mode Transition Tool版本3.3.2及更新版本）
  - CentOS版本6.4

    > 您可以使用符合所需軟體和硬體需求的Linux虛擬機器來安裝7-Mode Transition Tool。

- 64位元Oracle JRE 1.8更新45
- 7-Zip公用程式（「rpmfore-版本-0.3.6-1.el5.RF.x86_64。rpm」）

> 在設定7-Mode Transition Tool之前、必須先在Linux系統上安裝JRE 1.8和7-Zip公用程式。

在Linux上安裝7-Mode Transition Tool

您可以使用命令列介面、在Linux系統上安裝7-Mode Transition Tool。

- 您必須已檢閱7-Mode轉換工具的系統需求。

  在Linux上安裝7-Mode Transition Tool的系統需求

- 您必須擁有root使用者權限、才能安裝及啟動應用程式。

步驟

1. 請從NetApp支援網站下載「Tar.gz」檔案。

   "NetApp下載：軟體"

2. 將「tar・gz（tar・gz）檔案解壓縮至Linux系統中的目錄：

   "* tar -xzvf NetApp_7ModeTransitionTool_Setup.tar.gz -C *directory_path**

3. 將目錄變更為安裝目錄：

   '* CD *directory_path/NetApp_7ModeTransitionTool**

4. 設定7-Mode Transition Tool伺服器：

   "./configure （。/configure *）"

   這會在Linux系統上啟動7-Mode Transition Tool服務。

5. 確認7-Mode Transition Tool服務正在Linux系統上執行：

   「服務轉換-服務狀態」

範例

```
bash-4.2# tar -xzvf NetApp_7ModeTransitionTool_Setup.tar.gz -C
/root/Downloads/extracted_folder
bash-4.2# cd /root/Downloads/extracted_folder/NetApp_7ModeTransitionTool
bash-4.2# ./configure
bash-4.2# service transition-service status
The transition-service (NetApp 7-Mode Transition Tool server) is running.
PID=38384.
```

在Linux上解除安裝7-Mode Transition Tool

您可以使用命令列介面、在Linux上解除安裝7-Mode Transition Tool。

- 您必須已完成所有進行中的轉換。

> 安裝較新版本或重新安裝相同版本的工具、並不允許您存取由解除安裝的執行個體所啟動的轉換作業。

- 如果7-Mode Transition Tool正在執行、則必須停止該工具。

未在解除安裝時移除JRE。

步驟

1. 從您擷取7-Mode Transition Tool的位置執行下列命令、即可解除安裝7-Mode Transition Tool：

   "./unconfigure （。/取消設定*）"

2. 移除7-Mode Transition Tool目錄：
   a. 「* CD .*」
   b. 「* rm -rf netapp_7ModeTransitionTool*」

範例

```
bash-4.2# cd /root/Downloads/extracted_folder/NetApp_7ModeTransitionTool
bash-4.2# ./unconfigure
bash-4.2# cd ..
bash-4.2# rm -rf NetApp_7ModeTransitionTool
```

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.