產生FC區域計畫

ONTAP 7-Mode Transition

NetApp
May 03, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/ontap-7mode-transition/copy-free/concept_supported_configurations_for_generating_an_fc_zone_plan.html on May 03, 2022. Always check docs.netapp.com for the latest.

目錄

產生FC區域計畫 1
可產生FC區域計畫的支援組態 2

產生FC區域計畫

對於FC交換器、您必須在移轉評估報告中產生FC區域計畫、以便在移轉後設定區域、以便將啟動器主機和目標分組。

- 7-Mode系統、主機和叢集必須連線至相同的交換器。

  可產生FC區域計畫的支援組態

- 您必須在叢集上建立所需的目標SVM和FC LIF。
- 在目標SVM上建立的FC生命週期將會有WWPN、這與7-Mode WWPN不同。因此、在您為FCP轉換SAN時、請執行FC分區。

步驟

1. 在「收集與評估」區段中、按一下「新增系統」。
2. 在Add System（新增系統）視窗中、執行下列其中一項動作：
   - 新增單一系統：
     i. 輸入系統的FQDN或IP位址。
     ii. 輸入指定系統的使用者名稱和密碼。
     iii. 選取系統類型：
       - 儲存系統Data ONTAP
       - 主機：Microsoft Windows、Red Hat Linux Enterprise和VMware ESXi
       - FC交換器：Cisco與Brocade
   - 按一下*瀏覽*、然後選取包含多個系統認證的文字檔、即可新增多個系統。
3. 按一下「 * 新增 * 」。

   如果系統的評估狀態為「Ready（就緒）」、則您可以針對該系統執行轉換評估。

4. 使用FC區域計畫產生轉換評估報告：
   a. 選取系統（包括必要的FC交換器）以進行轉換評估。
   b. 按一下「建立轉換評估報告」。
   c. 在「Pair Systems and start FC Zone（配對系統並啟動FC區域規劃）」對話方塊中、選取7-Mode系統（單一控制器或HA配對）、連接至叢集的交換器、以及叢集中的SVM。

      如果您打算透過重新託管移轉的磁碟區、將FC LUN整合至單一SVM、請選取7-Mode HA配對和目標SVM。

      > 最佳做法是將FC LUN整合至單一SVM、以保留7-Mode單一系統映像（SSI）組態。

   如果您不打算整合FC LUN、則必須為每個7-Mode控制器和對應的目標SVM產生FC區域計畫。

   a. 按一下「* FC分區」以取得配對系統*。

b. 在「Create Transition Assessment Report（建立轉換評估報告）」對話方塊中、選取Data ONTAP 目標叢集的還原版本。

c. 指定報告檔案名稱的前置詞。

d. 按一下*產生報告*。

FC區域計畫是以「.Zip」檔案形式產生。此計畫包含根據7-Mode系統上的igroup組態所建立的區域。每個區域都包含一個啟動器WWPN和多個SVM目標WWPN。

您必須使用FC區域計畫來設定區域、以便將啟動器主機和目標分組、以便從叢集提供資料存取。

可產生FC區域計畫的支援組態

您必須瞭解7-Mode系統、主機、FC交換器和叢集的支援組態、才能產生FC區域計畫。移轉之後、您應該使用該計畫來設定叢集的區域。

視資料中心需求而定、7-Mode系統（單一控制器或HA配對）、主機和叢集可連接至相同架構中的交換器或不同架構。

下圖說明7-Mode系統、主機和叢集連接至同一網路架構中的交換器的組態：

下圖說明7-Mode系統和叢集連接至不同架構中的交換器的組態：



Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.