使用netGroups

ONTAP 9

NetApp
May 12, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/ontap/nfs-config/work-netgroups-task.html on May 12, 2022. Always check docs.netapp.com for the latest.

目錄

使用netGroups 1
使用網路群組總覽 1
將網路群組載入SVM 1
驗證netgroup定義的狀態 2

使用netGroups

使用網路群組總覽

您可以使用netGroups進行使用者驗證、並在匯出原則規則中比對用戶端。您可以從外部名稱伺服器（LDAP或NIS）存取netgroup、也可以使用「vserver services name-service netgroup load」命令、從統一資源識別元（URI）將netgroup載入SVM。

在使用netGroups之前、您必須確保符合下列條件：

- 不論來源（NIS、LDAP或本機檔案）為何、網路群組中的所有主機都必須同時擁有轉送（A）和反向（PTr）DNS記錄、才能提供一致的轉送和反向DNS查詢。

  此外、如果用戶端的IP位址有多筆PTr記錄、則所有這些主機名稱都必須是netgroup的成員、並具有對應的A記錄。

- 不論來源（NIS、LDAP或本機檔案）為何、netGroups中所有主機的名稱都必須正確拼寫、並使用正確的大小寫。在netGroups中使用的主機名稱若不一致、可能會導致非預期的行為、例如匯出檢查失敗。
- 在netGroups中指定的所有IPv6位址都必須依照RFC 5952中的指定來縮短和壓縮。

  例如、2011：hu9：0：0：0：0：3：1必須縮短為2011：hu9：3：1。

使用netGroups時、您可以執行下列作業：

- 您可以使用「vserver匯出原則netgroup檢查成員資格」命令來判斷用戶端IP是否為特定netgroup的成員。
- 您可以使用「vserver services name-service getxxbyyy netgrp」命令來檢查用戶端是否屬於netgroup。

  執行查詢的基礎服務是根據設定的名稱服務交換器順序來選取。

將網路群組載入SVM

您可以在匯出原則規則中使用符合用戶端的方法之一、就是使用netGroups中列出的主機。您可以將網路群組從統一資源識別元（URI）載入SVM、以取代使用儲存在外部名稱伺服器（「vserver services name-service netgroup loads」）中的網路群組。

Netgroup檔案在載入SVM之前、必須符合下列要求：

- 檔案必須使用與NIS相同的適當netgroup文字檔格式。

  此功能可在載入netgroup文字檔格式之前檢查其內容。ONTAP如果檔案包含錯誤、則不會載入、並會顯示訊息、指出您必須在檔案中執行的修正。更正錯誤後、您可以將netgroup檔案重新載入指定的SVM。

- netgroup檔案中主機名稱中的任何字母字元都應為小寫。
- 支援的檔案大小上限為5 MB。
- 巢狀網路群組支援的最大層級為1000。

- 在netgroup檔案中定義主機名稱時、只能使用主要DNS主機名稱。

  為了避免匯出存取問題、不應使用DNS CNAME/或循環配置資源記錄來定義主機名稱。

- netgroup檔案中三個群組的使用者和網域部分應保持空白、因為ONTAP 無法支援它們。

  僅支援主機/IP部分。

支援各主機的netgroup搜尋本機netgroup檔案。ONTAP載入netgroup檔案後ONTAP 、Syname會自動建立netgroup .byhost對應、以啟用逐主機的netgroup搜尋。這可大幅加速本機netgroup搜尋、以處理匯出原則規則來評估用戶端存取。

步驟

1. 從URI將網路群組載入SVM：

   「Vserver services name-service netgroup load -vserver *vserver_name*-source｛ftp | http | ftps| https｝：//*uni*」

   載入netgroup檔案並建置netgroup。byhost對應可能需要數分鐘的時間。

   如果要更新netgroup、您可以編輯該檔案、然後將更新的netgroup檔案載入SVM。

下列命令會從HTTP URL h+http://intranet/downloads/corp-netgroup+`:將netgroup定義載入名為VS1的SVM

```
vs1::> vserver services name-service netgroup load -vserver vs1
-source http://intranet/downloads/corp-netgroup
```

驗證netgroup定義的狀態

將netgroup載入SVM之後、您可以使用「vserver services name-service netgroup Status」命令來驗證netgroup定義的狀態。這可讓您判斷支援SVM的所有節點上的netgroup定義是否一致。

步驟

1. 將權限層級設為進階：

   "進階權限"

2. 驗證netgroup定義的狀態：

   「Vserver服務名稱服務網路群組狀態」

   您可以在更詳細的檢視畫面中顯示其他資訊。

3. 返回管理權限層級：

   「et -priv. admin」

設定權限層級後、下列命令會顯示所有SVM的netgroup狀態：

```
vs1::> set -privilege advanced

Warning: These advanced commands are potentially dangerous; use them only
when
         directed to do so by technical support.
Do you wish to continue? (y or n): y

vs1::*> vserver services name-service netgroup status
Virtual
Server    Node            Load Time           Hash Value
--------- --------------- -------------------
--------------------------------
vs1
          node1           9/20/2006 16:04:53
e6cb38ec1396a280c0d2b77e3a84eda2
          node2           9/20/2006 16:06:26
e6cb38ec1396a280c0d2b77e3a84eda2
          node3           9/20/2006 16:08:08
e6cb38ec1396a280c0d2b77e3a84eda2
          node4           9/20/2006 16:11:33
e6cb38ec1396a280c0d2b77e3a84eda2
```

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.