# 設定啟用了BranchCache的SMB共用區

ONTAP 9

NetApp
May 19, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/ontap/smb-admin/configure-branchcache-enabled-shares-concept.html on May 19, 2022. Always check docs.netapp.com for the latest.

# 目錄

設定啟用了BranchCache的SMB共用區 . . . . . 1
設定已啟用BranchCache的SMB共用區總覽 . . . . . 1
建立啟用BranchCache的SMB共用區 . . . . . 1
在現有的SMB共用區上啟用BranchCache . . . . . 2

# 設定啟用了BranchCache的SMB共用區

## 設定已啟用BranchCache的SMB共用區總覽

### 在SMB伺服器和分公司設定了BranchCache之後、您可以在SMB共用區上啟用內含您要允許分公司用戶端快取內容的BranchCache。

您可以在SMB伺服器上的所有SMB共用區上啟用「BranchCache快取」、或是以每個共用區為基礎來啟用「BranchCache快取」。

- 如果您以每共用區為基礎來啟用BranchCache、您可以在建立共用區或修改現有共用區時啟用BranchCache。

  如果您啟用現有SMB共用區的快取、ONTAP 只要您在該共用區上啟用了「BranchCache」、就會立即開始運算雜湊、並將中繼資料傳送給要求內容的用戶端。

- 如果隨後在該共用區上啟用了BranchCache、則任何與共用區有SMB連線的用戶端都不會獲得BranchCache支援。

  此版本可在SMB工作階段設定時、針對共用區通告BranchCache支援。ONTAP啟用了BranchCache之後、已建立工作階段的用戶端必須中斷連線並重新連線、才能使用此共用區的快取內容。

> ⓘ 如果SMB共用區上的BranchCache後來停用、ONTAP 則停止傳送中繼資料給要求的用戶端。需要資料的用戶端會直接從內容伺服器（SMB伺服器）擷取資料。

## 建立啟用BranchCache的SMB共用區

### 建立共用區時、您可以設定「BranchCache」共用區內容、在SMB共用區上啟用「BranchCache」。

關於這項工作

- 如果在SMB共用區上啟用了BranchCache、則共用區必須將離線檔案組態設定為手動快取。

  這是您建立共用時的預設設定。

- 您也可以在建立啟用了BranchCache的共用時指定其他選用的共用參數。
- 即使儲存虛擬機器（SVM）上未設定及啟用BranchCache、您仍可在共用區上設定「BranchCache」（BranchCache）屬性。

  不過、如果您想要共用區提供快取內容、則必須在SVM上設定及啟用BranchCache。

- 由於使用「-share-properties」參數時、沒有套用到共用區的預設共用屬性、因此除了使用以逗號分隔的清單來指定「BranchCache」共用屬性之外、您還必須指定要套用到共用區的所有其他共用屬性。
- 如需詳細資訊、請參閱「vserver CIFS共用create」命令的手冊頁。

步驟

1. 建立啟用了BranchCache的SMB共用區：+「vserver CIFS共用區create -vserver *vserver_name*-share

-name *share_name*-path *path*-share-properties BranchCache、…]

2. 使用「vserver CIFS共用show」命令、確認在SMB共用區上設定了「BranchCache共用區」屬性。

下列命令會在SVM VS1上建立一個名為「dATA」的啟用了BranchCache的SMB共用區、路徑為「/data」。根據預設、離線檔案設定設為「手動」：

```
cluster1::> vserver cifs share create -vserver vs1 -share-name data -path
/data -share-properties branchcache,oplocks,browsable,changenotify

cluster1::> vserver cifs share show -vserver vs1 -share-name data
                      Vserver: vs1
                        Share: data
     CIFS Server NetBIOS Name: VS1
                         Path: /data
             Share Properties: branchcache
                               oplocks
                               browsable
                               changenotify
           Symlink Properties: enable
      File Mode Creation Mask: -
 Directory Mode Creation Mask: -
                Share Comment: -
                    Share ACL: Everyone / Full Control
File Attribute Cache Lifetime: -
                  Volume Name: data
                Offline Files: manual
Vscan File-Operations Profile: standard
```

在單一SMB共用區上停用BranchCache

# 在現有的SMB共用區上啟用BranchCache

## 您可以將「BranchCache」共用內容新增至現有的共用內容清單、以在現有的SMB共用區上啟用「BranchCache」。

關於這項工作

- 如果在SMB共用區上啟用了BranchCache、則共用區必須將離線檔案組態設定為手動快取。

  如果現有共用的離線檔案設定未設定為手動快取、您必須修改共用區來設定。

- 即使儲存虛擬機器（SVM）上未設定及啟用BranchCache、您仍可在共用區上設定「BranchCache」（BranchCache）屬性。

  不過、如果您想要共用區提供快取內容、則必須在SVM上設定及啟用BranchCache。

- 當您將「BranchCache」共用內容新增至共用區時、會保留現有的共用設定和共用內容。

會將BranchCache共用屬性新增至現有的共用屬性清單。如需使用「vserver CIFS共用內容add」命令的詳細資訊、請參閱手冊頁。

步驟

1. 如有必要、請設定離線檔案共用設定以手動快取：
   a. 使用「vserver CIFS共用show」命令來判斷離線檔案共用設定。
   b. 如果離線檔案共用設定未設定為手動、請將其變更為所需的值：「vserver CIFS共用修改-vserver vserver_name -share-name share_name -offline檔案手冊」
2. 在現有的SMB共用區上啟用BranchCache：「vserver CIFS共用內容add -vserver vserver_name -share -name share_name -share-properties BranchCache」
3. 驗證是否已在SMB共用區上設定「vserver CIFS共用區show -vserver vserver_name -share-name share_name share_name」

下列命令可在SVM VS1上的現有SMB共用區「data2」上啟用BranchCache、路徑為「/data2」：

```
cluster1::> vserver cifs share show -vserver vs1 -share-name data2

                      Vserver: vs1
                        Share: data2
     CIFS Server NetBIOS Name: VS1
                         Path: /data2
             Share Properties: oplocks
                               browsable
                               changenotify
                               showsnapshot
           Symlink Properties: -
      File Mode Creation Mask: -
 Directory Mode Creation Mask: -
                Share Comment: -
                    Share ACL: Everyone / Full Control
File Attribute Cache Lifetime: 10s
                  Volume Name: -
                Offline Files: manual
Vscan File-Operations Profile: standard

cluster1::> vserver cifs share properties add  -vserver vs1 -share-name
data2 -share-properties branchcache

cluster1::> vserver cifs share show -vserver vs1 -share-name data2

                      Vserver: vs1
                        Share: data2
     CIFS Server NetBIOS Name: VS1
                         Path: /data2
             Share Properties: oplocks
                               browsable
                               showsnapshot
                               changenotify
                               branchcache
           Symlink Properties: -
      File Mode Creation Mask: -
 Directory Mode Creation Mask: -
                Share Comment: -
                    Share ACL: Everyone / Full Control
File Attribute Cache Lifetime: 10s
                  Volume Name: -
                Offline Files: manual
Vscan File-Operations Profile: standard
```

新增或移除現有SMB共用區上的共用內容

## 在單一SMB共用區上停用BranchCache

**Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.