为 Data ONTAP 创建 Snap Creator 用户

Snap Creator Framework

NetApp
January 17, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/snap-creator-framework/installation/task_creating_a_snap_creator_user_for_data_ontap_operating_in_7_mode.html on January 17, 2022. Always check docs.netapp.com for the latest.

目录

为 Data ONTAP 创建 Snap Creator 用户 1
为 7- 模式 Data ONTAP 创建 Snap Creator 用户 1
为集群模式 Data ONTAP 创建 Snap Creator 用户 2

为 Data ONTAP 创建 Snap Creator 用户

在安装 Snap Creator 之前，您应创建一个适用于 Data ONTAP 的 Snap Creator 用户。创建 Snap Creator 用户所遵循的过程取决于您的系统是在 7- 模式下运行 Data ONTAP 还是在集群模式 Data ONTAP 下运行。

为 7- 模式 Data ONTAP 创建 Snap Creator 用户

Snap Creator 使用 Data ONTAP API 与存储系统进行通信。要确保用户帐户仅被授予对 Snap Creator 的访问权限，请在每个存储控制器上创建一个新角色，组和用户。该角色将分配给该组，而该组包含该用户。此选项用于控制 Snap Creator 帐户的访问并限制其范围。

必须对安装了 Snap Creator 的每个存储控制器执行一次此操作步骤。

要使用 Data ONTAP 命令行界面（SSH，控制台连接或 Telnet）为在 7- 模式下运行的 Data ONTAP 创建 Snap Creator 用户，请完成以下步骤。

> 您不应直接从本文档中复制和粘贴命令；可能会出现错误，例如换行符和硬返回导致字符传输不正确。将此操作步骤中的命令复制并粘贴到文本编辑器中，验证这些命令，然后在命令行界面中输入它们。

1. 运行以下命令，创建一个角色，定义 Snap Creator 在存储系统上所需的权限：

```
useradmin role add rolename -a login-\*,api-snapshot-\*,api-system-\*,
api-ems-\*,api-snapvault-\*,api-snapmirror-\*,api-volume-\*,
api-lun-\*,api-cg-\*,api-nfs-\*,api-file-\*,api-license-\*,
api-net-\*api-clone-\*, api-options-get, api-wafl-sync
```

> 此步骤中显示的命令包括 Snap Creator 使用的所有 API 角色。但是，您可以通过仅包含所需角色来限制用户访问（例如，如果不使用 SnapMirror，则不需要 API-snapmirror-*）。

```
useradmin role add sc_role -a login-*,api-snapshot-*,api-system-*,api-
ems-*,api-snapvault-*,api-snapmirror-*,api-volume-*,
api-lun-*,api-cg-*,api-nfs-*,api-file-*,api-license-*, api-net-*, api-
clone-*, api-options-get, api-wafl-sync
```

2. 在存储系统上创建一个新组，并运行以下命令将新创建的角色分配给该组：

```
useradmin group add groupname -r rolename
```

```
useradmin group add snap_creator_group -r snap_creator_role
```

3. 运行以下命令创建用户帐户：

```
useradmin user add username -g groupname
```

```
useradmin user add snap_creator_user -g snap_creator_group
```

4. 输入帐户的密码。

在为 Snap Creator 创建配置文件时，请使用此受限帐户。

为集群模式 Data ONTAP 创建 Snap Creator 用户

对于集群模式 Data ONTAP ，您应为 Snap Creator 创建用户。但是，您创建的用户类型取决于集群模式 Data ONTAP 的版本。这两种类型的用户是集群用户和 Storage Virtual Machine （ SVM ）用户。

使用 _Snap Creator Framework 管理指南 _ 中定义的适当角色为您的 Data ONTAP 版本创建以下用户：

- 集群模式 Data ONTAP 8.2 之前的 Data ONTAP 版本：创建集群和 SVM 用户。
- 集群模式 Data ONTAP 8.2 或更高版本：创建 SVM 用户。

为了提高安全性，您应专门为 Snap Creator 创建一个 Data ONTAP 用户和角色。或者，您也可以使用其他用户帐户，例如 admin 或 vsadmin 。

有关使用命令行界面创建 Snap Creator 角色的详细信息，请参见相关参考。

这两种类型的用户都需要访问 Data ONTAPI 库。此外，无论版本如何，集群模式 Data ONTAP 也需要管理 LIF 。

这两个用户不可互换。例如，集群用户无权访问所需的 API 来执行某些操作，例如创建 Snapshot 副本。即使使用默认集群管理员帐户，也是如此。要使 Snap Creator 正常工作， SVM 帐户应使用 * vsadmin* 角色或客户创建的角色。

必须在使用 Snap Creator 的每个 SVM 和集群上执行一次此操作步骤。

为了便于使用，以下说明会提及管理员和 vsadmin 角色；但是，您可以将这些角色名称替换为您创建的角色。

> 您不应直接从本文档中复制和粘贴命令；可能会出现错误（例如，换行符和硬返回导致字符传输不正确）。将此操作步骤中的命令复制并粘贴到文本编辑器中，验证这些命令，然后在命令行界面中输入它们。

1. 在 SVM_name SVM 上创建具有适当角色（ vsadmin 或为用户创建的角色）的 SVM 用户 SVM_username01 ，并输入以下命令和用户密码以启用对 ONTAPI 库的访问：

```
security login create -username svm_username01
-vserver svm_name -application ontapi
-authmethod password -role vsadmin

Please enter a password for user 'svm_username01':
Please enter it again:
```

2. _ （仅适用于集群模式 Data ONTAP 8.2 之前的版本） _ 输入以下命令和用户密码以创建集群用户：

```
security login create -username svm_username02
-vserver svm_clustername -application ontapi
-authmethod password -role admin

Please enter a password for user 'svm_username02':
Please enter it again:
```

◦ 相关信息 *

用于在集群模式 Data ONTAP 中为 Snap Creator 用户创建角色的命令行界面命令

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.