用于置 SnapMirror 的参数

Snap Creator Framework

Zachary Wambold
August 04, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snap-creator-framework/administration/reference_parameters_to_set_up_snapmirror.html on October 27, 2021. Always check docs.netapp.com for the latest.

目□

用于□置 SnapMirror 的参数 1

用于□置 SnapMirror 的参数

要□ Snap Creator 服□器□置 SnapMirror， 需要使用多个参数。

参数	正在□置 ...	Description
ntap_snapmirror_update	"`Y` " 或 "`N` "	用于打□和□□ SnapMirror 更新功能。
ntap_snapmirror_caslated_update	"`Y` " 或 "`N` "	用于打□和□□□□ SnapMirror 更新功能。□是使用 SnapVault 目□卷□行的 SnapMirror 更新。 集群模式 Data ONTAP 不支持此功能。
snapmirror_volumes		指定要□行 SnapMirror 更新的源存□系□和卷的列表（例如，controller1 ： vol1， vol2， vol3 ； controller2 ： vol1 ； controller3 ： vol2， vol3 ）。* 注： * □于 VMware □件（ vSphere 和 vCloud ），此□□□置□ auto ： detect 。
snapmirror_lated_volumes		指定在 SnapVault 更新后要□行 SnapMirror 更新的 SnapVault 目□存□系□和卷的列表（例如， sec-controller1 ： vol1-sec， vol2-sec ）。如果源卷具有多个目□，□□□□制不支持此操作。 集群模式 Data ONTAP 不支持此功能。
ntap_snapmirror_wait		指定在 SnapMirror 目□上□建克隆之前完成 SnapMirror 更新□程的等待□□（以分□□□位）。如果 NTAP_clone_secondary □置□ Y，□ Snap Creator 将等待 SnapMirror 更新完成，然后再□□操作。 此□□只能用于 NTAP_clone_secondary 和 cloneVol 操作（当前□支持卷克隆）。

参数	正在□置 …	**Description**
ntap_snapmirror_use_snapshot	"`Y` " 或 "`N` "	如果□用此参数， SnapMirror 更新将使用新□建的 Snapshot 副本，从而在 SnapMirror 目□上□建 Snapshot 副本。* 注： * □于 NTAP_clone_secondary ，需要使用此副本，因□要在 SnapMirror 目□上□建克隆，需要 Snapshot 副本。
ntap_snapmirror_MAX_transfer		指定允□ SnapMirror 使用的最大□□（以 KBps □□位）。如果未□置此参数， SnapMirror 将使用最大可用□□。
snapmirror_qtree_include		指定要包括在 SnapMirror 更新中的主存□控制器和 qtree 路径的列表（例如， controller1 ： /vol/qtree1 ， /vol/volume/qtree2 ； controller2 ： /vol/volume/qtree1 ）。如果未使用此□□，□会□□卷下的所有 qtree 。通□使用此□□指定列表，将□□□列出的 qtree ；其余 qtree 将被忽略。

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.