# 为 Data ONTAP 创建 Snap Creator 用户

## Snap Creator Framework

NetApp
October 27, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snap-creator-framework/installation/task_creating_a_snap_creator_user_for_data_ontap_operating_in_7_mode.html on October 27, 2021. Always check docs.netapp.com for the latest.

# 目□

□ Data ONTAP □建 Snap Creator 用□ . . . . . 1
□ 7- 模式 Data ONTAP □建 Snap Creator 用□ . . . . . 1
□集群模式 Data ONTAP □建 Snap Creator 用□ . . . . . 2

# □ Data ONTAP □建 Snap Creator 用□

在安装 Snap Creator 之前，□□□建一个□用于 Data ONTAP 的 Snap Creator 用□。□建 Snap Creator 用□所遵循的□程取决于□的系□是在 7- 模式下□行 Data ONTAP □是在集群模式 Data ONTAP 下□行。

## □ 7- 模式 Data ONTAP □建 Snap Creator 用□

Snap Creator 使用 Data ONTAP API 与存□系□□行通信。要□保用□□□□被授予□ Snap Creator 的□□□限，□在□个存□控制器上□建一个新角色，□和用□。□角色将分配□□□，而□□包含□用□。此□□用于控制 Snap Creator □□的□□并限制其□□。

必□□安装了 Snap Creator 的□个存□控制器□行一次此操作□□。

要使用 Data ONTAP 命令行界面（ SSH ， 控制台□接或 Telnet ）□在 7- 模式下□行的 Data ONTAP □建 Snap Creator 用□，□完成以下□□。

> □不□直接从本文□中□制和粘□命令；可能会出□□□，例如□行符和硬返回□致字符□□不正□。将此操作□□中的命令□制并粘□到文本□□器中，□□□些命令，然后在命令行界面中□入它□。

1. □行以下命令，□建一个角色，定□ Snap Creator 在存□系□上所需的□限：

```
useradmin role add rolename -a login-\*,api-snapshot-\*,api-system-\*,
api-ems-\*,api-snapvault-\*,api-snapmirror-\*,api-volume-\*,
api-lun-\*,api-cg-\*,api-nfs-\*,api-file-\*,api-license-\*,
api-net-\*api-clone-\*, api-options-get, api-wafl-sync
```

> 此□□中□示的命令包括 Snap Creator 使用的所有 API 角色。但是，□可以通□□包含所需角色来限制用□□□（例如，如果不使用 SnapMirror ， □不需要 API-snapmirror-* ）。

```
useradmin role add sc_role -a login-*,api-snapshot-*,api-system-*,api-
ems-*,api-snapvault-*,api-snapmirror-*,api-volume-*,
api-lun-*,api-cg-*,api-nfs-*,api-file-*,api-license-*, api-net-*, api-
clone-*, api-options-get, api-wafl-sync
```

2. 在存□系□上□建一个新□，并□行以下命令将新□建的角色分配□□□：

```
useradmin group add groupname -r rolename
```

```
useradmin group add snap_creator_group -r snap_creator_role
```

3. □行以下命令□建用□□□：

```
useradmin user add username -g groupname
```

```
useradmin user add snap_creator_user -g snap_creator_group
```

4. □入□□的密□。

在□ Snap Creator □建配置文件□，□使用此受限□□。

# □集群模式 Data ONTAP □建 Snap Creator 用□

□于集群模式 Data ONTAP ， □□□ Snap Creator □建用□。但是，□□建的用□□型取决于集群模式 Data ONTAP 的版本。□□□□型的用□是集群用□和 Storage Virtual Machine （ SVM ）用□。

使用 _Snap Creator Framework 管理指南 _ 中定□的□当角色□□的 Data ONTAP 版本□建以下用□：

- 集群模式 Data ONTAP 8.2 之前的 Data ONTAP 版本：□建集群和 SVM 用□。
- 集群模式 Data ONTAP 8.2 或更高版本：□建 SVM 用□。

□了提高安全性，□□□□□ Snap Creator □建一个 Data ONTAP 用□和角色。或者，□也可以使用其他用□□□，例如 admin 或 vsadmin 。

有□使用命令行界面□建 Snap Creator 角色的□□信息，□参□相□参考。

□□□□型的用□都需要□□ Data ONTAPI □。此外，无□版本如何，集群模式 Data ONTAP 也需要管理 LIF 。

□□个用□不可互□。例如，集群用□无□□□所需的 API 来□行某些操作，例如□建 Snapshot 副本。即使使用默□集群管理□□□，也是如此。要使 Snap Creator 正常工作， SVM □□□使用 * vsadmin* 角色或客□□建的角色。

必□在使用 Snap Creator 的□个 SVM 和集群上□行一次此操作□□。

□了便于使用，以下□明会提及管理□和 vsadmin 角色；但是，□可以将□些角色名称替□□□□建的角色。

> □不□直接从本文□中□制和粘□命令；可能会出□□□（例如，□行符和硬返回□致字符□□不正□）。将此操作□□中的命令□制并粘□到文本□□器中，□□□些命令，然后在命令行界面中□入它□。

1. 在 SVM_name SVM 上□建具有□当角色（ vsadmin 或□用□□建的角色）的 SVM 用□ SVM_username01 ，并□入以下命令和用□密□以□用□ ONTAPI □的□□：

```
security login create -username svm_username01
-vserver svm_name -application ontapi
-authmethod password -role vsadmin

Please enter a password for user 'svm_username01':
Please enter it again:
```

2. _（□□用于集群模式 Data ONTAP 8.2 之前的版本）_ □入以下命令和用□密□以□建集群用□：

```
security login create -username svm_username02
-vserver svm_clustername -application ontapi
-authmethod password -role admin

Please enter a password for user 'svm_username02':
Please enter it again:
```

◦ 相□信息 *

用于在集群模式 Data ONTAP 中□ Snap Creator 用□□建角色的命令行界面命令

**Copyright Information**

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.