建立SnapCreator使用者Data ONTAP以供參考

Snap Creator Framework

NetApp
May 03, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/snap-creator-framework/installation/task_creating_a_snap_creator_user_for_data_ontap_operating_in_7_mode.html on May 03, 2022. Always check docs.netapp.com for the latest.

目錄

建立SnapCreator使用者Data ONTAP 以供參考 1
建立Snap Creator使用者、以便Data ONTAP 在7-Mode中運作 1
為叢集Data ONTAP 式的功能建立SnapCreator使用者 2

建立SnapCreator使用者Data ONTAP 以供參考

在安裝Snap Creator之前、您應該先建立Snap Creator使用者以供Data ONTAP 參考。建立Snap Creator使用者的程序取決於您的系統是以Data ONTAP 7-Mode或叢集Data ONTAP 式VMware執行。

建立Snap Creator使用者、以便Data ONTAP 在7-Mode中運作

SnapCreator使用Data ONTAP REST API與儲存系統進行通訊。若要確保使用者帳戶只能存取Snap Creator、請在每個儲存控制器上建立新的角色、群組和使用者。角色會指派給群組、而群組中包含該使用者。這會控制對SnapCreator帳戶的存取並限制其範圍。

您必須針對安裝SnapCreator的每個儲存控制器執行此程序一次。

若要使用Data ONTAP VMware CLI（Data ONTAP SSH、主控台連線或遠端登入）建立Snap Creator使用者、以便在7-Mode中運作、請完成下列步驟。

> 您不應直接從本文件複製及貼上命令、因為換行和硬退貨造成的字元傳輸不正確等錯誤可能會導致。將此程序中的命令複製並貼到文字編輯器、驗證命令、然後在CLI中輸入。

1. 執行下列命令、在儲存系統上建立角色、以定義Snap Creator所需的權限：

```
useradmin role add rolename -a login-\*,api-snapshot-\*,api-system-\*,
api-ems-\*,api-snapvault-\*,api-snapmirror-\*,api-volume-\*,
api-lun-\*,api-cg-\*,api-nfs-\*,api-file-\*,api-license-\*,
api-net-\*api-clone-\*, api-options-get, api-wafl-sync
```

> 此步驟所示的命令包括Snap Creator所使用的所有API角色。不過、您可以僅加入所需的角色來限制使用者存取（例如、如果不使用SnapMirror、則不需要API-SnapMirror-*）。

```
useradmin role add sc_role -a login-*,api-snapshot-*,api-system-*,api-
ems-*,api-snapvault-*,api-snapmirror-*,api-volume-*,
api-lun-*,api-cg-*,api-nfs-*,api-file-*,api-license-*, api-net-*, api-
clone-*, api-options-get, api-wafl-sync
```

2. 在儲存系統上建立新群組、然後執行下列命令、將新建立的角色指派給群組：

```
useradmin group add groupname -r rolename
```

```
useradmin group add snap_creator_group -r snap_creator_role
```

3. 執行下列命令來建立使用者帳戶：

```
useradmin user add username -g groupname
```

```
useradmin user add snap_creator_user -g snap_creator_group
```

4. 輸入帳戶的密碼。

建立SnapCreator的組態檔時、請使用此受限帳戶。

為叢集Data ONTAP 式的功能建立SnapCreator使用者

對於叢集Data ONTAP 式的功能、您應該為Snap Creator建立使用者。不過、您所建立的使用者類型取決於叢集Data ONTAP 式的版本。這兩種使用者分別是叢集使用者和儲存虛擬機器（SVM）使用者。

針對Data ONTAP 您的版本的資訊、建立下列使用者、並依照_Snap Creator Framework管理指南_中所定義的適當角色：

- 叢集式版本的發行版、不只發行叢集式版本、更能建立叢集和SVM使用者。Data ONTAP Data ONTAP
- 叢集Data ONTAP 式的SVM 8.2或更新版本：建立SVM使用者。

為了提高安全性、您應該特別為Data ONTAP Snap Creator建立一個不穩定的使用者和角色。或者、您也可以使用其他使用者帳戶、例如admin或vsadmin。

如需使用CLI建立Snap Creator角色的詳細資訊、請參閱相關參考資料。

這兩種使用者都需要存取Data ONTAPI程式庫。此外、無論Data ONTAP 版本為何、叢集式的更新也需要管理LIF。

這兩個使用者不可互換。例如、叢集使用者無法存取所需的API來執行某些動作、例如建立Snapshot複本。即使您使用預設的叢集管理帳戶、也是如此。SVM帳戶應使用* vsadmin*角色或客戶建立的角色、以便Snap Creator正常運作。

您必須在使用SnapCreator的每個SVM和叢集上執行此程序一次。

為了方便使用、下列指示會提及管理員和vsadmin角色；不過、您可以將這些角色名稱取代為您所建立的角色。

> 您不應直接從本文件複製及貼上命令、否則可能會產生錯誤（例如換行和硬回傳所造成的字元傳輸不正確）。將此程序中的命令複製並貼到文字編輯器、驗證命令、然後在CLI中輸入。

1. 在SVM_nameSVM上建立具有適當角色（vsadmin或為使用者建立的角色）的SVM使用者SVM_username01、並輸入下列命令和使用者密碼、以啟用對ONTAPI程式庫的存取：

```
security login create -username svm_username01
-vserver svm_name -application ontapi
-authmethod password -role vsadmin

Please enter a password for user 'svm_username01':
Please enter it again:
```

2. _（Data ONTAP 僅適用於叢集式的版本）_輸入下列命令和使用者密碼、以建立叢集使用者：

```
security login create -username svm_username02
-vserver svm_clustername -application ontapi
-authmethod password -role admin

Please enter a password for user 'svm_username02':
Please enter it again:
```

相關資訊

CLI命令、可在叢集Data ONTAP 式的功能表中為Snap Creator使用者建立角色

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.