由 SnapDrive 管理的 RDM LUN 的限制

Snapdrive for Unix

NetApp
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapdrive-unix/linux-administration/concept_limitations_of_rdm_luns_managed_by_snapdrive.html on October 26, 2021. Always check docs.netapp.com for the latest.

目□

由 SnapDrive 管理的 RDM LUN 的限制 1

由 SnapDrive 管理的 RDM LUN 的限制

SnapDrive 在配置 RDM LUN 方面有一些限制。□必□了解可能影□□境的限制。

- RDM LUN 不能用作□□磁□或系□磁□。
- SnapDrive 在 Internet 小型□算机系□接口（ iSCSI ）□境中不支持 RDM LUN 。
- SnapDrive 不支持在子操作系□中使用 MPIO ， 但 VMware ESX 服□器支持 MPIO 。
- 如果□□□□□ ` FC_` ， □ SnapDrive 会忽略在 CLI 命令中指定的 igroup ， 而 igroup 会由虚□接口自□□建。
- □可以重命名，移□或□除作□ `sg3_utils` 一部分□□的 ` /usr/bin/resscan-scsi-bus.sh` 脚本，以避免将 RDM LUN 的数量限制□八个。

> 如果要在 `sg3_utils` 中保留 ` /usr/bin/resscan-scsi-bus.sh` 并避免将 RDM LUN 的数量限制□ 8 个，□必□□建一个包装程序脚本 ` /root/dynamic-lun-rescan` ， 然后从此脚本□行 ` /usr/bin/rescan scsi-bus.sh` ， 并使用□□ ` -w ， ` ` 和` assign ` 。`

以下是已修改的 ` /root/dynamic-lun-rescan.sh` 内容的示例：

```
#cat /root/dynamic-lun-rescan.sh
#Wrapper script used to call the actual rescan script.
/usr/bin/rescan-scsi-bus.sh -w -c -r
```

- 与 VMware ESX 服□器相□的限制 *
- □个子操作系□可以配置四个 SCSI 控制器，□个 SCSI 控制器可以映射到 16 个□□。

  但是，□个控制器会保留一个□□，因此□共可以将 60 个（ 16 个 * ， 4 个 - 4 个） RDM LUN 映射到子操作系□。

- □个 ESX 服□器最多可映射到 256 个 RDM LUN 。
- 相□信息 *

SnapDrive for UNIX 中支持 VMware VMotion

配置□用于 UNIX 的 SnapDrive 的虚□存□控制台

配置 RDM LUN 的注意事□

"www.vmware.com/pdf/vsphere4/r40/vsp_40_config_max.pdf"

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.