storage connect 命令

Snapdrive for Unix

NetApp
October 26, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapdrive-unix/aix/concept_guidelines_for_thestorage_connectcommand.html on October 26, 2021. Always check docs.netapp.com for the latest.

目□

storage connect 命令 1
storage connect 命令的准□ 1
使用 SnapDrive storage connect 命令所需的信息 1
□接具有磁□□，主机卷和文件系□的 LUN 3
使用共享□源□接□有 LUN 3

storage connect 命令

SnapDrive storage connect` 命令可将存□□体□接到主机。使用此命令可以将 LUN 和存□□体□接到主机

使用 SnapDrive storage connect` 命令□接到：

- LUN
- 直接在 LUN 上□建的文件系□
- 在 LUN 上□建的磁□□，主机卷和文件系□

□入 SnapDrive storage connect` 命令将 LUN □接到主机□， SnapDrive for UNIX 将□行必要的□□和映射。它不会修改 LUN 内容。

storage connect 命令的准□

要使用 SnapDrive storage connect` 命令，□需要遵循一些准□。

包含 LVM □体的存□具有特殊要求。要使用 SnapDrive storage connect` 命令□接 LVM □体，必□□建存□，以便存□□次□□中的□个□体都只有一个下一个□体的□例。例如，□可以使用 SnapDrive storage connect` 命令□接一个存□□次□□，□存□□次□□包含一个磁□□（ dg1 ），一个主机卷（ hostvol1 ）和一个文件系□（ fs1 ）。但是，□不能使用 SnapDrive storage connect` 命令□接一个□次□□，其中一个磁□□（ dg1 ）包含□个主机卷（ hostvol1 和 hostvol2 ）和□个文件系□（ fs1 和 fs2 ）。

使用 SnapDrive storage connect 命令所需的信息

使用 SnapDrive storage connect` 命令□，□需要提供一些信息。此信息有助于□正□使用命令。

要求	参数
指定 LUN ， 直接在 LUN 上□建的文件系□或要□接到主机的 LVM □体。 • 如果□接一个或多个 LUN ， □第一个参数必□使用□形式的 LUN 名称，此名称用于指定存□系□名称 ，卷名称以及卷中 LUN 的名称。 要指定其他 LUN ， 如果新 LUN 与上一个 LUN 位于同一存□系□和卷上，□可以□独使用 LUN 名称。否□，□可以指定新的存□系□名称和卷名称（或□指定卷名称）来替□先前的□。 • 如果□□接的是直接在 LUN 上□建的文件系□，□必□包含 LUN 名称的□格式以及 ` -nolvm` □□。 • 如果将 LUN □接到磁□□，主机卷和文件系□，□必□使用 ` -FS` 和 ` -hostvol` □□指定文件系□和主机卷。主机卷必□包含磁□□的名称。	LUN （` -lun` ）
` lun_name_`	□ ` -lun` □□提供的第一个□必□包括存□系□名称，卷和 LUN 名称。要□接同一卷上的多个 LUN ， □可以在第一个路径名称中提供完整信息后，□ ` -LUN` □□使用相□路径名称。当 SnapDrive for UNIX 遇到相□路径名称□，它会□□与上一个 LUN 位于同一卷上的 LUN 。要□接不在同一卷上的其他 LUN ， □□入□个 LUN 的完整路径名称。
其他 LUN	` lun_name_` （□或短格式）
□ ` -FS` 提供的 ` file_spec_` 是□接直接在 LUN 上□建的文件系□□文件系□挂□点的名称。	文件系□（` -fs file-specs` ）
` 文件系□名称 _`	在不激活主机 LVM 的情况下□接在 LUN 上□建的文件系□。
` -nolvm`	
要□接主机卷上的文件系□，□□行以下操作： □提供的 ` -fs *file_spec*` 和 ` -hostvol *file_spec*` 用于□□要□接到新主机的 LVM 文件系□，磁□□和主机卷。 □□接的存□□次□□必□包含磁□□，主机卷和文件系□。□必□□ ` -fs` 和 ` -hostvol` 指定一个□。` -hostvol` □必□包含磁□□的名称。	主机卷（` -hostvol file-spect` ）

要求	参数
` *disk_group_name*` 和 ` 主机 *volume_name*`	可□：使用 ` -nt操作` □□将存□□接到新位置，而无需在主机文件系□表中□建条目。默□情况下， storage connect 命令会□建永久性挂□。□意味着，在 AIX 主机上□建 LVM 存□□体□， SnapDrive for UNIX 会自□□建存□，挂□文件系□，然后在主机文件系□表中□文件系□放置一个条目。
` - noperit`	~
• 可□： * 建□□主机使用默□ igroup ， 而不是提供 igroup 名称。	igroup 名称（` -igroup` ）
` ig_name_`	` - fstype`
` _ □型 _`	`vmtype`
` _ □型 _`	• 可□： * 指定用于 SnapDrive for UNIX 操作的文件系□和卷管理器的□型。
` - mntopts`	~

□接具有磁□□，主机卷和文件系□的 LUN

要使用 SnapDrive storage connect` 命令□接具有磁□□，主机卷和文件系□的 LUN ， □需要遵循以下□法。

□入以下命令：

` * SnapDrive storage connect -fs *file_spec* -hostvol *file_spec* -lun *lon_lun_name* [*lun_name*…] [-igroup *ig_name* [*ig_name*…]] 【 -noperisture] 【 -mntets *options*】 【 *-fstype _type*】 【 -vmtype *type*]*`

示例：□接在 LUN 上□建的文件系□

```
# snapdrive storage connect -fs /mnt/fs -lun f270-221-189:/vol/vol0/lun111
-nolvm
mapping lun(s) ... done
discovering lun(s) ... done
LUN f270-221-189:/vol/vol0/lun111 connected
- device filename(s): /dev/vx/dmp/fas2700_939
```

使用共享□源□接□有 LUN

如果向使用共享磁□□或文件系□的主机集群配置添加了新□点，□需要遵循其他□法。

` * SnapDrive storage connect -fs *file_spec* -lun *lon_lun_name* LUN_name…] [-mntets options]*`

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.