smo clone create 命令

SnapManager Oracle

NetApp
September 23, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapmanager-oracle/unix-administration/reference_the_smosmsapclone_create_command.html on October 26, 2021.
Always check docs.netapp.com for the latest.

目□

smo clone create 命令 1
□法 1
Parameters 1
示例 4

smo clone create 命令

□可以□行 clone create 命令□□□的数据□□建克隆。□可以从主存□或二□存□克隆□□。

□法

```
        smo clone create
-profile profile_name
[-backup-id backup_guid \| -backup-label backup_label_name \| -current\]
-newsid new_sid
\[-host target_host\]
[-label clone_label]
\[-comment string\]
-clonespec full_path_to_clonespec_file
\[-asminstance -asmusername asminstance_username  -asmpassword
asminstance_password\]]
\[-syspassword syspassword\]
\[-reserve \{yes \| no \| inherit\}\]
\[-from-secondary \{-copy-id id\}\]
\[-no-resetlogs \| -recover-from-location path1 \[, path2\]\]\[-taskspec
taskspec\]
\[-dump\]
\[-quiet \| -verbose\]
```

Parameters

- * 配置文件名称 *

  指定要克隆的数据□。配置文件包含数据□的□□符和其他数据□信息。

- **-backup-id guid**

  使用指定 GUID 克隆□□。GUID 由 SnapManager 在□建□□□生成。□可以使用 smo backup list-verbose 命令□示□个□□的 GUID 。

- **-backup-label backup_laber_name**

  指定使用指定□□名称克隆□□。

- * - 当前 *

  指定从数据□的当前状□□建□□和克隆。

  > 如果数据□□于 nodarchivelog 模式， SnapManager 将□建脱机□□。

- * — newsid new_sid*

□克隆的数据□指定一个新的唯一 Oracle 系□□□符。系□□□符□最多□八个字符。Oracle 不允□在同一主机上同□□行具有相同系□□□符的□个数据□。

- * — host target_host*

  指定□在其上□建克隆的主机。

- * — label clone_label *

  指定克隆的□□。

- * —注□字符串 *

  指定用于描述此克隆的可□注□。必□将字符串用□引号括起来。

  > 某些 shell 会□除引号。如果□的 shell □□如此，□必□使用反斜杠（ \ ）□□引号。例如，□可能需要□入： " This is a coming\"

- **-clonSpec full_path_to_clonesore_file**

  指定克隆□□ XML 文件的路径。此路径可以是相□路径名称，也可以是□□路径名称。

- * — asminstance*

  指定用于登□到 ASM □例的凭据。

- * — asmusername asminstance_username*

  指定用于登□到 ASM □例的用□名。

- * — asmpassword asminstance_password*

  指定用于登□到 ASM □例的密□。

- * — sysspassword sysspassword*

  指定 sys 特□用□的密□。

  > 如果□ sys 特□用□提供的数据□凭据与□ sys 特□用□提供的数据□凭据不同，□必□□ sys 特□用□提供密□。

- * —□留 *

  将 -reserve □□□置□ yes 可□保□新克隆卷□用卷保□空□□留。将 -reserve □□□置□ no 可□保□新克隆卷□□卷保□空□□留。将 -reserve □□□置□□承可□保新克隆□承父 Snapshot 副本的空□□留特性。默□□置□ No

  下表介□了克隆方法及其□克隆□建操作及其 -reserve □□的影□。可以使用任一方法克隆 LUN 。

克隆方法	Description	□果

LUN cloning	A new clone LUN is created within the same volume.	When the -reserve option for a LUN is set to yes, space is reserved for the full LUN size within the volume.
Volume cloning	A new FlexClone is created, and the clone LUN exists within the new clone volume. Uses the FlexClone technology.	When the -reserve option for a volume is set to yes, space is reserved for the full volume size within the aggregate. +

- 从二□卷 * □建的文件（ -copy-idcopy_id） *

  指定 SnapManager □将已受保□的□□副本克隆到二□存□。如果未指定此□□，□ SnapManager 会从主存□克隆副本。

  □当指定 -from-secondary □□□，都必□指定 -copy-id □□。如果二□存□系□上有多个□□，□使用 -copy-id □□指定二□存□上□使用□个□□副本□行克隆。

  > 如果□使用的是在 7- 模式下□行的 Data ONTAP ，□必□□ -copy-id □□指定有效□。但是，如果使用的是集群模式 Data ONTAP ，□不需要 -copy-id □□。

- **-no-resetlogs**

  指定跳□恢□数据□，□行 DBNEWID □用程序，并且在□建克隆□不使用重置日志打□数据□。

- * —从位置恢□ *

  指定□□日志□□的外部□□日志位置， SnapManager 会从外部位置□取□□日志文件并使用□些文件□行克隆。

- * — taskspec*

  指定用于克隆操作的□□理活□或后□理活□的任□□□ XML 文件。□必□提供任□□□ XML 文件的完整路径。

- * —□□ *

  指定在克隆□建操作后收集□□文件。

- * —静默 *

在控制台中□□示□□消息。默□□置□□示□□和警告消息。

- * —□□ *

  在控制台中□示□□，警告和信息性消息。

示例

以下示例将使用□此克隆□建的克隆□□克隆□□：

```
smo clone create -profile SALES1 -backup-label full_backup_sales_May
-newsid
CLONE -label sales1_clone -clonespec
/opt/<path>/smo/clonespecs/sales1_clonespec.xml
```

```
Operation Id [8abc01ec0e794e3f010e794e6e9b0001] succeeded.
```

- 相□信息 *

正在□建克隆□□

从□□克隆数据□

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.