建任前，任后和策略脚本

SnapManager Oracle

NetApp
August 06, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapmanager-oracle/windows/task_creating_pretask_post_task_and_policy_scripts.html on October 26, 2021. Always check docs.netapp.com for the latest.

目□

□建任□前，任□后和策略脚本 1
示例脚本 2

□建任□前，任□后和策略脚本

使用 SnapManager 可以□□□理活□，后□理活□以及□□，□原和克隆操作的策略任□□建脚本。□必□将脚本放置在正□的安装目□中，才能□行 SnapManager 操作的□□理活□，后□理活□和策略任□。

- □□理和任□后脚本内容 *

所有脚本都必□包括以下内容：

- 特定操作（□□，描述和□行）
- （可□）□定□的□境□量
- 特定□□□理代□（返回代□（ RC ））

> □必□包含正□的□□□理代□才能□□脚本。

可以将任□前脚本用于多□用途，例如，在 SnapManager 操作□始之前清理磁□空□。例如，□□可以使用任□后脚本来估□ SnapManager 是否有足□的磁□空□来完成此操作。

- 策略任□脚本内容 *

□可以□行策略脚本，而无需□行□□，描述和□行等特定操作。□脚本包含□定□的□境□量（可□）和特定的□□□理代□。

策略脚本会在□行□□，□原和克隆操作之前□行。

- 支持的格式 *

□展名□ .cmd 的命令文件可用作□□理脚本和后□理脚本。

> 如果□□ shell 脚本文件，□ SnapManager 操作不会□□。要解决此□□，□必□在□件目□中提供命令文件，然后重新□行 SnapManager 操作。

- 脚本安装目□ *

脚本的安装目□会影□脚本的使用方式。□可以将脚本放置在目□中，并在□行□□，□原或克隆操作之前或之后□行此脚本。□必□将脚本放置在表中指定的目□中，并在指定□□，□原或克隆操作□以可□方式使用□脚本。

> 在使用脚本□行 SnapManager 操作之前，□必□□保 plugins 目□具有可□行□限。

活□	□□	□原	克隆
□□理	<default_installation_directory>\plugins\backup\create\pre	<default_installation_directory>\plugins\restore\create\pre	<default_installation_directory>\plugins\clone\create\pre

后□理	<default_installation_directory>\plugins\backup\create\post	<default_installation_directory>\plugins\restore\create\post	<default_installation_directory>\plugins\clone\create\post
基于策略	<default_installation_directory>\plugins\backup\create\policy	<default_installation_directory>\plugins\restore\create\policy	<default_installation_directory>\plugins\clone\create\policy

- 脚本位置示例 *

以下是安装目□路径中可用的□□和克隆操作的任□前和任□后脚本示例：

- <default_installation_directory>\plugins\examples\backup\create\pre
- <default_installation_directory>\plugins\examples\backup\create\post
- <default_installation_directory>\plugins\examples\clone\create\pre
- <default_installation_directory>\plugins\examples\clone\create\post
- 可以在脚本中更改的内容 *

如果要□建新脚本，□只能更改描述和□行操作。□个脚本都必□包含以下□量： context， timeout 和 parameter 。

□在脚本的描述功能中所述的□量必□在脚本□□声明。□可以在 parameter=（ ）中添加新参数□，然后使用 execute 函数中的参数。

示例脚本

下面是一个脚本示例，其中包含用□指定的返回代□，用于估算 SnapManager 主机中的空□：

```
@echo off
REM $Id:
//depot/prod/capstan/Rcapstan_ganges/src/plugins/windows/examples/clone/cr
eate/policy/validate_sid.cmd#1 $
REM $Revision: #1 $ $Date: 2011/12/06 $
REM
REM

set /a EXIT=0

set name="Validate SID"
set description="Validate SID used on the target system"
set parameter=()

rem reserved system IDs
set INVALID_SIDS=("ADD" "ALL" "AND" "ANY" "ASC" "COM" "DBA" "END" "EPS"
"FOR" "GID" "IBM" "INT" "KEY" "LOG" "MON" "NIX" "NOT" "OFF" "OMS" "RAW"
"ROW" "SAP" "SET" "SGA" "SHG" "SID" "SQL" "SYS" "TMP" "UID" "USR" "VAR")
```

```
if /i "%1" == "-check" goto :check
if /i "%1" == "-execute" goto :execute
if /i "%1" == "-describe" goto :describe

:usage:
    echo usage: %0 "{ -check | -describe | -execute }"
    set /a EXIT=99
    goto :exit

:check
    set /a EXIT=0
    goto :exit

:describe
    echo SM_PI_NAME:%name%
    echo SM_PI_DESCRIPTION:%description%
    set /a EXIT=0
    goto :exit

:execute
    set /a EXIT=0

    rem SM_TARGET_SID must be set
    if "%SM_TARGET_SID%" == "" (
        set /a EXIT=4
        echo SM_TARGET_SID not set
        goto :exit
    )

    rem exactly three alphanumeric characters, with starting with a letter
    echo %SM_TARGET_SID% | findstr "\<[a-zA-Z][a-zA-Z0-9][a-zA-Z0-9]\>"
>nul
    if %ERRORLEVEL% == 1 (
        set /a EXIT=4
        echo SID is defined as a 3 digit value starting with a letter.
[%SM_TARGET_SID%] is not valid.
        goto :exit
    )

    rem not a SAP reserved SID
    echo %INVALID_SIDS% | findstr /i \"%SM_TARGET_SID%\" >nul
    if %ERRORLEVEL% == 0 (
        set /a EXIT=4
        echo SID [%SM_TARGET_SID%] is reserved by SAP
        goto :exit
```

```
    )

    goto :exit



:exit
    echo Command complete.
    exit /b %EXIT%
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.