SnapManager 中的数据保□□介

SnapManager Oracle

NetApp
October 26, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snapmanager-oracle/windows/concept_how_snapmanager_retains_backups_on_the_local_storage.html on October 26, 2021. Always check docs.netapp.com for the latest.

目□

SnapManager 中的数据保□□介 1
SnapManager 如何在本地存□上保留□□ 1
□行数据保□的注意事□ 3
使用后脚本保□数据□□□ 3

SnapManager 中的数据保□□介

SnapManager 支持数据保□，以保□二□或三□存□系□上的□□。□必□在源卷和目□卷之□□置 SnapMirror 和 SnapVault □系。

□可以使用命令行界面（ CLI ）和□形用□界面（ GUI ）中的□□后脚本来保□主存□系□上的□□。

SnapManager 如何在本地存□上保留□□

通□ SnapManager ，□可以□建符合保留策略的□□，□些策略指定□在本地存□上保留多少成功的□□。□可以指定在配置文件中□□定数据□保留的成功□□数。

□可以□以下□□建□□：

- 主存□上□天□□ 10 天
- 主存□上□月□□ 2 个月
- 在二□存□上□行 7 天的□日□□
- 在二□存□上□周□□ 4 周
- 在二□存□上□月□□ 6 个月

□于 SnapManager 中的□个配置文件，□可以更改以下非受限保留□的□：

- □小□
- □天
- □周
- □月

SnapManager 会通□考□保留□数（例如 15 个□□）和保留期限（例如 10 天的□日□□）来□定是否□保留□□。如果□□的期限超□□其保留□□置的保留期限，或者□□数量超□保留数量，□□□将□期。例如，如果□□□数□ 15 （ SnapManager 已成功□建□□ 15 ），并且□ 10 天的□日□□□置了持□□□要求，□五个最旧的成功□□将□期。

□□□期后， SnapManager 会□放或□除已□期的□□。SnapManager 始□会保留上次□建□□。

SnapManager □会□入保留□数中成功□□的数量，不会考□以下因素：

□□不包含在保留□数中	其他□□信息
□□失□	SnapManager 会保留有□□□成功和失□的信息。□然□□失□只需要□少的存□□空□，但□可能希望将其□除。失□的□□会保留在存□□中，直到□□除它□□止。
指定□无限制保留的□□或其他保留□的□□	SnapManager 不会□除指定无限制保留的□□。此外，SnapManager □考□同一保留□中的□□（例如，SnapManager □考□□小□保留□数的□小□□□）。

从本地存□挂□的□□	挂□ Snapshot 副本后，□些副本也会□行克隆，因此不符合保留条件。如果 Snapshot 副本已克隆，□ SnapManager 无法□除□些副本。
用于在本地存□上□建克隆的□□	SnapManager 会保留用于□建克隆的所有□□，但不会将其□□□□保留□数。

SnapManager □□个保留□提供默□保留□数和持□□□。例如，□于□小□保留□□数，默□情况下，SnapManager 会保留四个□小□□□。□可以在□建或更新配置文件□覆□□些默□□并□置□些□，也可以更改 SMO.config 文件中保留□数和持□□□的默□□。

如果本地□□根据其保留策略□期，□会□除□些□□。

与□机数据□□□□程不同，在□□□日志□□操作中， SnapManager 不会□□重做日志文件。在□行□□□日志□□操作之前，□必□添加任□前脚本以□□重做日志文件。任□前脚本必□□行 alter system switch logfile 命令。

以下示例□示了 SnapManager 根据三个□日□□保留策略（将□数□置□保留 3 ）□各□□型的□□□行的操作：

□□日期	Status	已□行保留策略操作	□明
5/10	成功	保留	□是最新成功的□□，因此会保留□□□。
5/9	成功，已克隆	跳□	SnapManager 不会在保留策略□数中考□用于克隆的□□。成功□□的□数会省略此□□。
5/8.	成功，已挂□	跳□	SnapManager 不会在保留策略□数中考□挂□的□□。成功□□的□数会省略此□□。
5/7.	失□	跳□	失□的□□不会□入在内。
5/5.	成功	保留	SnapManager 可□保□第二次成功的□日□□。
5/3.	成功	保留	SnapManager 可□保□是第三次成功的□日□□。
5/2	成功	□除	SnapManager 会□算此成功□□的数量，但在 SnapManager □天成功完成三次□□后，此□□将被□除。

- 相□信息 *

"NetApp 支持站点上的文□： mysupport.netapp.com"

□行数据保□的注意事□

□必□了解□行数据保□□的某些注意事□。

- 要从二□系□□行克隆或□原操作，必□将目□卷挂□到命名空□中并正□□出。
- □必□通□将 SnapDrive 配置参数 check-export-permission-nfs-clone 的□□置□ off 来禁用此参数。

  NetApp 支持站点上的 SnapDrive for UNIX 文□包含有□ check-export-permission-nfs-clone 参数的追加信息。

- □必□□二□存□系□中□求的二□存□卷配置 SnapMirror □系。
- □于 7- 模式 Data ONTAP ， □必□在二□存□系□中□□求的二□存□ qtree 配置 SnapVault □系。
- 如果要□集群模式 Data ONTAP 使用 SnapVault 后脚本，□必□□用□定□的 SnapMirror □□定□策略和□□。

  SnapVault 后脚本支持集群模式 Data ONTAP 卷以及 SnapMirror □系□型 DP 和 XDP 。NetApp 支持站点上的 ONTAP 文□包含有□配置 SnapMirror 和 SnapVault 的信息。

"NetApp 支持站点上的文□： mysupport.netapp.com"

SnapManager 中的数据保□所需的□可□

□必□□保在主存□系□和二□存□系□上安装并□用数据保□所需的□可□。

主存□系□可接收 Oracle 数据□的最新事□更新，存□数据并□数据□提供本地□□保□。主存□系□□□□数据□数据文件，日志文件和控制文件。二□存□系□充当受保□□□的□程存□。

要保□数据，必□在主存□系□上安装并□用以下□可□：

> ⓘ 如果要在二□存□系□上□用数据保□，□必□在二□存□系□上安装和□用□些□可□。

- 以 7- 模式（ 7.3.1 或更高版本）□行的 Data ONTAP 或集群模式 Data ONTAP （ 8.2 或更高版本）
- SnapVault
- SnapRestore
- SnapMirror
- 克隆需要 FlexClone 。

  此外，只有在将 SnapDrive 配置□在 SAN □境中使用 FlexClone □，存□区域网□（ SAN ）才需要 FlexClone 。

- 相□的□□，例如 Internet 小型□算机系□接口（ iSCSI ）或光□通道（ FC ）

使用后脚本保□数据□□□

在主存□系□和二□存□系□之□建立 SnapMirror 或 SnapVault □系□，□可以通□

SnapManager 使用后脚本保□数据□□□。□可以从 SnapManager 命令行界面和 GUI □□□操作的后□理活□使用默□后□理脚本。

□可以使用 default_install_directory\plugins\backup\create\post 中提供的以下默□后□理脚本：

- 如果□使用的是在 7- 模式下□行的 Data ONTAP， □□ SnapMirror 后脚本 mirror_the_backup.cmd
- 如果□使用的是在 7- 模式下□行的 Data ONTAP， □□ SnapVault PostScript_the_backup.cmd
- 如果使用的是集群模式 Data ONTAP， □□ SnapMirror 后脚本 mirror_the_backup_cDOT.cmd
- 如果使用的是集群模式 Data ONTAP， □□ SnapVault PostScript_the_backup_cDOT.cmd

有□□□信息，□参□ default_install_directory\plugins 上的 readme.txt 。

SnapManager 3.1 或更早版本□□克隆操作提供□□理或后□理脚本。SnapManager 3.2 或更高版本□□□和□原操作提供了□□理和后□理脚本。□可以使用□些脚本在□□或□原操作之前或之后□行。

> 提供的脚本□供参考。它□已通□□用于 Windows 的 SnapDrive 7.0 或更高版本的□□，但可能不□用于所有□境。□□根据二□保□要求自定□脚本。□些脚本不□用于 6.2 之前的 SnapDrive 版本。

示例后脚本

□可以参考示例脚本并根据□境□建自定□脚本，以□行□像和存□。示例脚本位于 default_install_directory\plugins\backup\create\post 。

mirror_the_backup.cmd

如果□使用的是在 7- 模式下□行的 Data ONTAP， □可以使用此示例脚本□像□□。它包括三个操作（□□，描述和□行），并在脚本末尾□行□些操作。□脚本□包括□□消息□理，代□□ 0 到 4 和 > 4 ：

```
@echo off
REM $Id:
//depot/prod/capstan/main/src/plugins/windows/examples/backup/create/post/
Mirror_the_backup.cmd#1 $
REM
REM Copyright \(c\) 2011 NetApp, Inc.
REM All rights reserved.
REM
REM
REM This is a sample post-task script to mirror the volumes to the
secondary storage after successful backup operation.
REM|-------------------------------------------------------------------------
-----------------------------------------|
REM| Pre-requisite/Assumption:
|
REM|   SnapMirror relationship for the requested secondary storage volumes
must be configured in Secondary storage. |
```

```
REM|-------------------------------------------------------------------------
-----------------------------------------|
REM
REM
REM This script can be used from the SnapManager graphical user interface
(GUI) and command line interface (CLI).
REM
REM To execute the post-task script for the backup operation from
SnapManager GUI, follow these steps:
REM  1. From the Backup wizard > Task Specification page > Post-Tasks tab
> select the post-task scripts from the Available Scripts section.
REM
REM
REM To execute the post-task script for the backup operation from
SnapManager CLI, follow these steps:
REM  1. create a task specification XML file.
REM  2. Add the post-script name in the <post-tasks> tag of the XML file.
REM
REM Example:
REM              <post-tasks>
REM                 <task>
REM                    <name>Mirror the backup</name>
REM                      <description>Mirror the backup</description>
REM                </task>
REM              <post-tasks>
REM
REM
REM
REM IMPORTANT NOTE: This script is provided for reference only. It has
been tested with SnapDrive 6.3.0 for Windows but may not work in all
environments.  Please review and then customize based on your secondary
protection requirements.
REM
set /a EXIT=0
set name="Mirror the backup"
set description="Mirror the backup"
set parameter=()


if /i "%1" == "-check" goto :check
if /i "%1" == "-execute" goto :execute
if /i "%1" == "-describe" goto :describe

:usage
        echo usage: %0 ^{ -check ^| -describe ^| -execute ^}
        set /a EXIT=99
```

```
        goto :exit

:check
        set /a EXIT=0
        goto :exit

:describe
        echo SM_PI_NAME:%name%
        echo SM_PI_DESCRIPTION:%description%
        echo SM_PRIMARY_MOUNT_POINTS : %SM_PRIMARY_MOUNT_POINTS%
        set /a EXIT=0
        goto :exit

REM - Split the comma-separated PRIMARY_MOUNT_POINTS and Mirror the
PRIMARY_MOUNT_POINTS one-by-one.

:execute
        set /a EXIT=0

        echo "execution started"

        REM FOR %%G IN (%SM_PRIMARY_MOUNT_POINTS%) DO echo %%G

        FOR %%V IN (%SM_PRIMARY_MOUNT_POINTS%) DO sdcli snap update_mirror
-d %%V

        if "%ERRORLEVEL%" NEQ "0" (
           set /a EXIT=4
           exit /b %EXIT%
        )

        echo "execution ended"

        goto :exit

:exit
        echo Command complete.
        exit /b %EXIT%
```

vault_the_backup.cmd

如果□使用的是在 7- 模式下□行的 Data ONTAP ， □可以使用此示例脚本来存□□□。它包括三个操作（□□，描述和□行），并在脚本末尾□行□些操作。□脚本□包括□□消息□理，代□□ 0 到 4 和 > 4 ：

```
@echo off
REM $Id:
```

```
//depot/prod/capstan/main/src/plugins/windows/examples/backup/create/post/
Vault_the_backup.cmd#1 $
REM
REM Copyright \(c\) 2011 NetApp, Inc.
REM All rights reserved.
REM
REM
REM This is a sample post-task script to vault the qtrees to the secondary
storage after successful backup operation.
REM|-------------------------------------------------------------------------
-----------------------------------------|
REM| Pre-requisite/Assumption:
|
REM|   SnapVault relationship for the requested secondary storage qtrees
must be configured in Secondary storage. |
REM|-------------------------------------------------------------------------
-----------------------------------------|
REM
REM
REM This script can be used from the SnapManager graphical user interface
(GUI) and command line interface (CLI).
REM
REM To execute the post-task script for the backup operation from
SnapManager GUI, follow these steps:
REM  1. From the Backup wizard > Task Specification page > Post-Tasks tab
> select the post-task scripts from the Available Scripts section.
REM
REM
REM To execute the post-task script for the backup operation from
SnapManager CLI, follow these steps:
REM  1. create a task specification XML file.
REM  2. Add the post-script name in the <post-tasks> tag of the XML file.
REM
REM Example:
REM              <post-tasks>
REM                 <task>
REM                    <name>Vault the backup</name>
REM                    <description>Vault the backup</description>
REM                </task>
REM              <post-tasks>
REM
REM IMPORTANT NOTE: This script is provided for reference only. It has
been tested with SnapDrive 6.3.0 for Windows but may not work in all
environments.  Please review and then customize based on your secondary
protection requirements.
REM
```

```
REM
REM
REM
REM
set /a EXIT=0
set name="Vault the backup"
set description="Vault the backup"
set parameter=()



if /i "%1" == "-check" goto :check
if /i "%1" == "-execute" goto :execute
if /i "%1" == "-describe" goto :describe

:usage
        echo usage: %0 ^{ -check ^| -describe ^| -execute ^}
        set /a EXIT=99
        goto :exit

:check
        set /a EXIT=0
        goto :exit

:describe
        echo SM_PI_NAME:%name%
        echo SM_PI_DESCRIPTION:%description%
        echo SM_PRIMARY_SNAPSHOTS_AND_MOUNT_POINTS :
%SM_PRIMARY_SNAPSHOTS_AND_MOUNT_POINTS%
        set /a EXIT=0
        goto :exit

REM Split the colon-separated SM_PRIMARY_SNAPSHOTS_AND_MOUNT_POINTS And
SnapVault the mountpoints one-by-one

:execute
        set /a EXIT=0

        echo "execution started"

        FOR %%A IN (%SM_PRIMARY_SNAPSHOTS_AND_MOUNT_POINTS%) DO FOR /F
"tokens=1,2 delims=:" %%B IN ("%%A") DO sdcli snapvault archive  -a %%B
-DS %%C %%B

        if "%ERRORLEVEL%" NEQ "0" (
           set /a EXIT=4
           exit /b %EXIT%
```

```
        )
        echo "execution ended"

        goto :exit

:exit
        echo Command complete.
        exit /b %EXIT%
```

mirror_the_backup_cDOT.cmd

如果□使用的是集群模式 Data ONTAP ， □可以使用此示例脚本□像□□。它包括三个操作（□□，描述和□行），并在脚本末尾□行□些操作。□脚本□包括□□消息□理，代□□ 0 到 4 和 > 4 ：

```
@echo off
REM $Id:
//depot/prod/capstan/main/src/plugins/windows/examples/backup/create/post/
Mirror_the_backup_cDOT.cmd#1 $
REM
REM  Copyright \(c\) 2011 NetApp, Inc.
REM All rights reserved.
REM
REM
REM This is a sample post-task script to mirror the volumes to the
secondary storage after successful backup operation.
REM|-----------------------------------------------------------------------
-----------------------------------------|
REM| Pre-requisite/Assumption:
|
REM|   SnapMirror relationship should be set for the primary volumes and
secondary volumes                          |
REM|-----------------------------------------------------------------------
-----------------------------------------|
REM
REM
REM This script can be used from the SnapManager graphical user interface
(GUI) and command line interface (CLI).
REM
REM To execute the post-task script for the backup operation from
SnapManager GUI, follow these steps:
REM  1. From the Backup wizard > Task Specification page > Post-Tasks tab
> select the post-task scripts from the Available Scripts section.
REM
REM
REM To execute the post-task script for the backup operation from
SnapManager CLI, follow these steps:
```

```
REM  1. create a task specification XML file.
REM  2. Add the post-script name in the <post-tasks> tag of the XML file.
REM
REM Example:
REM             <preposttask-specification xmlns="http://www.netapp.com">
REM               <task-specification>
REM                 <post-tasks>
REM                   <task>
REM                     <name>"Mirror the backup for cDOT"</name>
REM                   </task>
REM                 </post-tasks>
REM               </task-specification>
REM             </preposttask-specification>
REM
REM
REM
REM IMPORTANT NOTE: This script is provided for reference only. It has
been tested with SnapDrive 7.0 for Windows but may not work in all
environments.  Please review and then customize based on your secondary
protection requirements.
REM
set /a EXIT=0
set name="Mirror the backup cDOT"
set description="Mirror the backup cDOT"
set parameter=()



if /i "%1" == "-check" goto :check
if /i "%1" == "-execute" goto :execute
if /i "%1" == "-describe" goto :describe

:usage
        echo usage: %0 ^{ -check ^| -describe ^| -execute ^}
        set /a EXIT=99
        goto :exit

:check
        set /a EXIT=0
        goto :exit

:describe
        echo SM_PI_NAME:%name%
        echo SM_PI_DESCRIPTION:%description%
        set /a EXIT=0
        goto :exit
```

```
REM - Split the comma-separated SM_PRIMARY_MOUNT_POINTS then Mirror the
PRIMARY_MOUNT_POINTS one-by-one.

:execute
        set /a EXIT=0

        echo "execution started"

        REM FOR %%G IN (%SM_PRIMARY_MOUNT_POINTS%) DO powershell.exe -file
"c:\snapmirror.ps1" %%G < CON

        powershell.exe -file "c:\snapmirror.ps1"
%SM_PRIMARY_FULL_SNAPSHOT_NAME_FOR_TAG% < CON


        if "%ERRORLEVEL%" NEQ "0" (
           set /a EXIT=4
           exit /b %EXIT%
        )

        echo "execution ended"

        goto :exit

:exit
        echo Command complete.
        exit /b %EXIT%
```

vault_the_backup_cDOT.cmd

如果□使用的是集群模式 Data ONTAP ， □可以使用此示例脚本来存□□□。它包括三个操作（□□，描述和□行），并在脚本末尾□行□些操作。□脚本□包括□□消息□理，代□□ 0 到 4 和 > 4 ：

```
@echo off
REM $Id:
//depot/prod/capstan/main/src/plugins/windows/examples/backup/create/post/
Vault_the_backup_cDOT.cmd#1 $
REM
REM  Copyright \(c\) 2011 NetApp, Inc.
REM All rights reserved.
REM
REM
REM This is a sample post-task script to do vault update to the secondary
storage after successful backup operation.
REM|-----------------------------------------------------------------------
--------------------------------------------|
```

```
REM| Pre-requsite/Assumption:
|
REM|   Vaulting relationship with policy and rule needs to be established
between primary and secondary storage volumes |
REM|-----------------------------------------------------------------------
-------------------------------------------|
REM
REM
REM This script can be used from the SnapManager graphical user interface
(GUI) and command line interface (CLI).
REM
REM To execute the post-task script for the backup operation from
SnapManager GUI, follow these steps:
REM
REM  1. From the Backup wizard > Task Specification page > Post-Tasks tab
> select the post-task scripts from the Available Scripts section.
REM  2. You can view the parameters available in the post-task script in
the Parameter section of the Task Specification page.
REM  3. Provide values to the following parameters:
REM     SNAPSHOT_LABEL     - Label Name to be set for snapshots before
doing the vault update
REM
REM FOR WINDOWS ITS ADVISED TO USE THE post-task script FROM THE GUI BY
SAVING THE BELOW SPEC XML AND GIVING THIS IN THE GUI LOAD XML FILE .
REM
REM To execute the post-task script for the backup operation from
SnapManager CLI, follow these steps:
REM  1. create a task specification XML file.
REM  2. Add the post-script name in the <post-tasks> tag of the XML file .
REM Example:
REM             <preposttask-specification xmlns="http://www.netapp.com">
REM               <task-specification>
REM                 <post-tasks>
REM                   <task>
REM                     <name>"Vault the backup for cDOT"</name>
REM                     <parameter>
REM                     <name>SNAPSHOT_LABEL</name>
REM                     <value>TST</value>
REM                     </parameter>
REM                   </task>
REM                 </post-tasks>
REM               </task-specification>
REM             </preposttask-specification>
REM
REM
REM IMPORTANT NOTE: This script is provided for reference only. It has
```

```
been tested with SnapDrive 7.0.0 for Windows but may not work in all
environments.
Please review and then customize based on your secondary protection
requirements.
REM
REM
REM Need to take care of the parameter variable, its not like shell script
array handling, so declare a new variable
REM for one more argument and set that variable SM_PI_PARAMETER in the
describe method. Then only that variable will be
REM Visible in the GUI task specification wizard else it wont list.

set /a EXIT=0
set name="Vault the backup for cDOT"
set description="Vault the backup For cDOT volumes"
set parameter=SNAPSHOT_LABEL :

if /i "%1" == "-check" goto :check
if /i "%1" == "-execute" goto :execute
if /i "%1" == "-describe" goto :describe

:usage
        echo usage: %0 ^{ -check ^| -describe ^| -execute ^}
        set /a EXIT=99
        goto :exit

:check
        set /a EXIT=0
        goto :exit

:describe
        echo SM_PI_NAME:%name%
        echo SM_PI_DESCRIPTION:%description%
    echo SM_PI_PARAMETER:%parameter%

        set /a EXIT=0
        goto :exit

REM Split the colon-separated SM_PRIMARY_SNAPSHOTS_AND_MOUNT_POINTS And
SnapVault the mountpoints one-by-one

:execute
        set /a EXIT=0

    echo "execution started"

    powershell.exe -file "c:\snapvault.ps1"
```

```
%SM_PRIMARY_FULL_SNAPSHOT_NAME_FOR_TAG%  %SNAPSHOT_LABEL% < CON

        if "%ERRORLEVEL%" NEQ "0" (
           set /a EXIT=4
           exit /b %EXIT%
        )
    echo "execution ended"

        goto :exit

:exit
        echo Command complete.
        exit /b %EXIT%
```

□建或更新 POST 脚本

□可以□建新的 POST 脚本，也可以使用 default_install_directory\plugins\backup\create\post 中提供的脚本。

□必□以特定方式□脚本□行□□□整，以便可以在 SnapManager 操作的上下文中□行□脚本。根据□期操作，可用□入参数和返回代□□定□建脚本。

1. □建新脚本或使用可用的示例脚本。
2. 根据需要修改或包括函数，□量和参数。
3. 保存自定□脚本。
4. 在后□理任□□□ XML 文件中添加脚本名称和所需□入，或者通□□□正□的脚本和□入参数从□形用□界面提供□入。

   □不必在任□□□ XML 文件中提供二□存□□□信息。

   - 相□信息 *

□ SnapManager 操作□建任□□□文件和脚本

□建后□理，任□□□文件

通□ SnapManager ，□可以□□□操作□建后□理，任□□□的 XML 文件，其中包括 SnapMirror 或 SnapVault 后脚本。通□□些脚本，□可以将□□□像或存□到二□存□。

1. 打□新的 XML 文件。

   □可以在 default_install_directory\plugins\examples □看任□□□ XML 文件示例。

2. 将脚本名称添加□□入参数。
3. 保存任□□□ XML 文件。

使用后□理任□□□□像卷

通□ SnapManager for Oracle， □可以在 Windows □境中□行□□操作后使用脚本□像卷。

1. □建任□□□ XML 文件。
2. 在 XML 文件中，□入脚本名称作□□入参数。
3. 保存任□□□ XML 文件。
4. 使用以下命令□建数据□到二□存□的受保□□□。

   □建受保□的□□□，□必□在 -taskSpec □□后面提供已保存任□□□ XML 文件的完整路径。

   示例： smobackup create -profile test_profile -full -online -taskspecC ： \\mirror\\snapmirror.xml

以下示例□示了使用 7- 模式 Data ONTAP □的后□理任□□□□□：

```
#     <post-tasks>
#               <task>
#                   <name>Mirror the backup</name>
#                    <description>Mirror the backup</description>
#               </task>
#             <post-tasks>
```

以下示例□示了使用集群模式 Data ONTAP □的后□理任□□□□□：

```
# <task-specification>
#              <post-tasks>
#                  <task>
#                   <name>"Vault the backup for cDOT"</name>
#                    <parameter>
#                    <name>SNAPSHOT_LABEL</name>
#                   <value>TST</value>
#                    </parameter>
#                  </task>
#                </post-tasks>
#              </task-specification>
#            </preposttask-specification>
```

使用后□理任□□□来存□ **qtree**

通□ SnapManager for Oracle， □可以在 Windows □境中□行□□操作后使用脚本来存□ qtree 。

1. □建任□□□ XML 文件。
2. 在 XML 文件中，□入脚本名称作□□入参数。

3. 保存任□□□ XML 文件。
4. 使用以下命令□建数据□到二□存□的受保□□□。

   □建受保□的□□□，□必□在 -taskSpec □□后面提供已保存任□□□ XML 文件的完整路径。

   示例： smobackup create -profile test_profile -full -online -taskspec" C ： \\mirror\\snapvault.xml"

以下示例□示了使用 7- 模式 Data ONTAP □的后□理任□□□□□：

```
# <post-tasks>
#                <task>
#                  <name>Vault the backup</name>
#                   <description>Vault the backup</description>
#              </task>
#         <post-tasks>
```

以下示例□示了使用集群模式 Data ONTAP □的后□理任□□□□□：

```
# <task-specification>
#                <post-tasks>
#                  <task>
#                   <name>"Vault the backup for cDOT"</name>
#                 <parameter>
#                    <name>SNAPSHOT_LABEL</name>
#                    <value>TST</value>
#                    </parameter>
#                  </task>
#                </post-tasks>
#              </task-specification>
#            </preposttask-specification>
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.