支持不使用 ASMLib 的 ASM 数据库

SnapManager Oracle

NetApp
January 17, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/snapmanager-oracle/unix-administration/concept_supported_scripts.html on January 17, 2022. Always check docs.netapp.com for the latest.

目录

支持不使用 ASMLib 的 ASM 数据库 1
支持的脚本 1
使用脚本支持不使用 ASMLib 的 ASM 数据库的限制 1
部署和运行脚本 2
支持 ASM 数据库而不使用 ASMLib 的示例脚本 4

支持不使用 ASMLib 的 ASM 数据库

默认情况下， SnapManager 支持不使用 ASMLib 的 ASM 。基本要求是，必须对用于 ASM 磁盘组的设备进行分区。

如果未安装 ASMLib ，则在执行以下操作时，与 ASM 磁盘组相关的设备权限将更改为 root： disk： disk：

- 重新启动主机
- 使用基于卷的 SnapRestore （ VBSR ）从主存储还原数据库
- 从二级存储还原数据库

您可以通过为 SMO.conf 中的 oracleasma.support.without .asmlib 配置变量分配 true 来设置适当的设备权限。每当在主机中添加或删除新设备时，系统都会在 initasmdisks 文件中添加或删除与 ASM 磁盘组相关的设备。initasmdisks 文件位于 /etc/initasmdisks 。

例如，如果设置 oracleasma.support.without .asmlib=true ，然后执行备份挂载，则会将新设备添加到 initasmdisks 中。重新启动主机后，启动脚本会保留设备权限和所有权。

> oracleasma.support.without 。 asmlib 的默认值为 false 。

- 相关信息 *

支持的分区设备

支持的脚本

使用 asmmain.sh 和 asmquerydisk.sh 脚本可以更改网格用户，组和用户，所有这些脚本都用于查询 ASM 磁盘。必须始终从根执行这些脚本。

asmmain.sh 是从任何添加或删除设备的操作中调用的主脚本文件。asmmain.sh 脚本会在内部调用另一个脚本，该脚本需要从具有 Oracle 网格凭据的根目录执行。此脚本将查询 ASM 磁盘组的设备，然后在 initasmdisk 文件中添加这些条目，并添加这些设备的权限和所有权。您可以根据您的环境以及仅用于匹配 /dev/mapper/* P1 的正则表达式更改此文件的权限和所有权。

asmquerydisk.sh 脚本用于查询磁盘列表，该列表用于创建 ASM 磁盘组。您必须根据您的配置为 ORACLE_BASE ， ORACLE_HOME 和 ORACLE_SID 分配值。

这些脚本位于 /opt/netapp/smO/plugins/examples/noasmlib 。但是，在主机上启动 SnapManager for Oracle 服务器之前，必须将这些脚本移至 /opt/netapp/smO/plugins/noasmlib 。

使用脚本支持不使用 ASMLib 的 ASM 数据库的限制

您必须了解在不使用 ASMLib 的情况下使用脚本支持 ASM 数据库的某些限制。

- 这些脚本可为任何内核版本提供备用解决方案，但前提是未安装 ASMLib 。
- 脚本的权限设置方式必须使 root ， grid ， oracle 或等效用户能够访问这些脚本。

- 这些脚本不支持从二级位置进行还原。

部署和运行脚本

您可以部署和运行 asmmain.sh 和 asmquerydisk.sh 脚本，以支持 ASM 数据库，而无需 ASMLib 。

这些脚本不遵循预脚本或后脚本语法，启用 intitasmdisks 时会调用工作流。您可以在脚本中更改与配置设置相关的任何内容。建议通过执行快速试运行来验证脚本中的所有内容是否均按预期工作。

> 这些脚本不会因故障而对系统造成损害，也不会影响系统。执行这些脚本可更新与 ASM 相关的磁盘以获得适当的权限和所有权，从而使这些磁盘始终处于 ASM 实例控制之下。

1. 使用已分区的磁盘创建 ASM 磁盘组。
2. 在磁盘组上创建 Oracle 数据库。
3. 停止适用于 Oracle 服务器的 SnapManager 。

   > 在 RAC 环境中，您需要对所有 RAC 节点执行此步骤。

4. 修改 smo.conf 以包含以下参数：

   a. oracleasma.support.without .asmlib = true
   b. oracleasma.support.without .asmlib.ownership = true
   c. oracleasm.support.without.asmlib.username = ASM 实例环境的用户名
   d. oracleasm.support.without.asmlib.groupname = ASM 实例环境的组名称

   这些修改仅为绝对路径设置权限，这意味着，将仅为 dm-* 设备设置权限，而不是分区设备。

5. 修改 /opt/netapp/smO/plugins/examples/noasmlib 中提供的插件脚本，以便在这些脚本中包含您的配置设置。
6. 在主机上启动 SnapManager for Oracle 服务器之前，请将脚本复制到 /opt/netapp/smO/plugins/noasmlib 。
7. 导航到 /opt/netapp/smo 目录，然后运行以下脚本执行试运行： sh plugins/noasmlib/asmmain.sh

   此时将创建 etc/initasmdisks 文件，该文件是所使用的主文件。

   您可以确认 etc/initasmdisks 文件包含与已配置的 ASM 数据库相关的所有设备，例如：

```
chown -R grid:oinstall /dev/mapper/360a98000316b61396c3f394645776863p1
         chmod 777 /dev/mapper/360a98000316b61396c3f394645776863p1
         chown -R grid:oinstall
/dev/mapper/360a980003754322f7a2b433469714239p1
         chmod 777 /dev/mapper/360a980003754322f7a2b433469714239p1
         chown -R grid:oinstall
/dev/mapper/360a980003754322f7a2b433469714241p1
         chmod 777 /dev/mapper/360a980003754322f7a2b433469714241p1
         chown -R grid:oinstall
/dev/mapper/360a980003754322f7a2b433469714243p1
         chmod 777 /dev/mapper/360a980003754322f7a2b433469714243p1
```

8. 启动适用于 Oracle 服务器的 SnapManager 。
9. 通过将以下内容添加到 SnapDrive.conf file.disconnect -luns-before-vbsr=on 来配置 SnapDrive for UNIX
10. 重新启动适用于 UNIX 的 SnapDrive 服务器。

> 在 RAC 环境中，您需要对所有 RAC 节点执行步骤 3 到步骤 10 。

创建的 /etc/initasmdisks 文件必须从其中一个启动脚本或 rc3.d 中新定义的脚本执行在 oracleha 服务启动之前，应始终执行 /etc/initasmdisks 文件。

示例

```
# ls -ltr *ohasd*
          lrwxrwxrwx 1 root root 17 Aug  7 02:34 S96ohasd ->
/etc/init.d/ohasd
          lrwxrwxrwx 1 root root 17 Aug  7 02:34 K15ohasd ->
/etc/init.d/ohasd
```

在以下示例中，默认情况下， sh -x/etc/initasmdisks 不可用，您需要将其附加为 ohasd 脚本中函数 `stt_stack` （） 的第一行：

```
start_stack()
{
sh -x /etc/initasmdisks
# see init.ohasd.sbs for a full rationale case $PLATFORM in Linux
}
```

支持不使用 **ASMLib** 的 **Oracle RAC ASM** 数据库

如果使用的是 Oracle RAC 数据库，则每当在主 RAC 节点中执行操作时，都必须使用 initasmdisks 文件更新 RAC 节点。

如果从主节点登录到 RAC 节点不需要身份验证，则 asmmain.sh 会对所有 RAC 节点执行 initasmdisks 的安全复制（ SCP ）。每当进行还原时，都会调用主节点的 initasmdisks 文件，并且可以更新 asmmain.sh 脚本，以便在所有 RAC 节点中调用相同的脚本。

创建的 /etc/initasmdisks 文件必须从其中一个启动脚本或 rc3.d 中新定义的脚本执行在 oracleha 服务启动之前，应始终执行 /etc/initasmdisks 文件。

支持不使用 **ASMLib** 的 **Oracle 10g ASM** 数据库

如果使用的是 Oracle 10g ，则 asmcmd 命令不可用于列出磁盘。您可以使用 SQL 查询获取磁盘列表。

disk_list.sql 脚本包含在示例目录中提供的现有脚本中，用于支持 SQL 查询。执行 theasmquerydisk.sh 脚本时，必须手动执行 disk_list.sql 脚本。在 asmquerydisk.sh 文件中添加了示例脚本行以及注释。此文件可以放置在 /home/grid 位置或您选择的其他位置。

支持 **ASM** 数据库而不使用 **ASMLib** 的示例脚本

示例脚本位于 SnapManager for Oracle 安装目录的 plugins/examples/noasmlib 目录中。

asmmain.sh

```
#!/bin/bash
griduser=grid
gridgroup=oinstall

# Run the script which takes the disklist from the asmcmd
# use appropriate user , here grid user is being used to run
# asmcmd command.
su -c "plugins/noasmlib/asmdiskquery.sh" -s /bin/sh grid
cat /home/grid/disklist

# Construct the final file as .bak file with propre inputs
awk -v guser=$griduser -v ggroup=$gridgroup '/^\/dev\/mapper/ { print
"chown -R "guser":"ggroup" "$1; print "chmod 777 " $1; }'
/home/grid/disklist > /etc/initasmdisks.bak

# move the bak file to the actual file.
mv /etc/initasmdisks.bak /etc/initasmdisks

# Set full full permission for this file to be called while rebooting and
restore
chmod 777 /etc/initasmdisks

# If the /etc/initasmdisks needs to be updated in all the RAC nodes
# or /etc/initasmdisks script has to be executed in the RAC nodes, then
the following
```

```
# section needs to be uncommented and used.
#
# Note: To do scp or running scripts in remote RAC node via ssh, it needs
password less login
# for root user with ssh keys shared between the two nodes.
#
# The following 2 lines are used for updating the file in the RAC nodes:
# scp /etc/initasmdisks root@racnode1:/etc/initasmdisks
# scp /etc/initasmdisks root@racnode2:/etc/initasmdisks
#
# In order to execute the /etc/initasmdisks in other RAC nodes
# The following must be added to the master RAC node /etc/initasmdisks
file
# from the asmmain.sh script itself. The above scp transfer will make sure
# the permissions and mode for the disk list contents are transferred to
the other RAC nodes
# so now appending any command in the /etc/initasmsdisks will be retained
only in the master RAC node.
# The following lines will add entries to the /etc/initasmsdisks file in
master RAC node only. When this script is executed
#  master RAC node, /etc/initasmdisks in all the RAC nodes will be
executed.
# echo 'ssh racnode1 /etc/initasmdisks' >> /etc/initasmdisks
# echo 'ssh racnode2 /etc/initasmdisks' >> /etc/initasmdisks
```

asmquerydisk.sh

```
#!/bin/bash
export  ORACLE_BASE=/u01/app/oracle
export ORACLE_HOME=/u01/app/grid/product/11.2.0.3/grid
export ORACLE_SID=+ASM
export  PATH=$ORACLE_HOME/bin:$PATH

# Get the Disk List and save this in a file called dglist.
asmcmd lsdsk  > /home/grid/disklist

# In oracle 10g the above used command 'asmcmd' is not available so use
SQL
# query can be used to take the disk list. Need to uncomment the following
# line and comment the above incase oracle 10g is being in use.
# The disk_list.sql script is availbe in this noasmlib examples folder
itself
# which can be modified as per customer needs.
# sqlplus "/as sysdba" @/home/grid/disk_list.sql > /home/grid/disklist
```

disk_list.sql

```
# su - oracle
-bash-4.1$ cat disk_list.sql
select path from v$asm_disk;
exit
-bash-4.1$
```

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.