Creating clone specifications

SnapManager Oracle

Aksel Davis
February 05, 2021

This PDF was generated from https://docs.netapp.com/us-en/snapmanager-oracle/unix-administration/task_creating_clone_specifications.html on August 06, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Creating clone specifications 1
Clone specification example 5

Creating clone specifications

SnapManager for Oracle uses a clone specification XML file, which includes the mappings, options, and parameters for use in the clone operation. SnapManager uses this information to determine where to place the files it clones and how to handle diagnostic information, control files, parameters, and so on.

You can create the clone specification file by using the SnapManager graphical user interface (GUI), command-line interface (CLI), or a text editor.

When you create the clone specification file by using a text editor, you must save it as a .xml file. You can use this XML file for other clone operations.

You can also create a clone specification template and then customize it. You can use the smo clone template command or in the GUI, use the Clone wizard.

SnapManager for Oracle adds a version string to any clone specification template that it generates. SnapManager for Oracle assumes the latest version for any clone specification file that lacks a version string.

If you want to perform remote cloning, do not change the default locations of the data files, redo log files, and control files in the clone specification file. If you change the default location, SnapManager fails to create the clone or creates the clone on a database that does not support Snapshot capability. Therefore, the automatic creation of profile fails.

> Though mount point and ASM disk group information are editable from the GUI, you can only change the file name and not the file locations.

You can execute a task multiple times, either with the same or different parameter and value combinations.

1. Open a text file and enter text as shown in the following example:

```
<clone-specification xmlns="http://www.example.com>
     <storage-specification/>
     <database-specification/>
 </clone-specification>
```

2. In the storage specification component, enter the mount points for the data files.

   The storage specification lists the locations for the new storage created for the clone such as data file mount points and raw devices. These items must be mapped from the source to the destination.

   The following example displays the data file mount point syntax that you use in the clone specification:

```
<mountpoint>
     <source>/mnt/path/source_data file_mountpoint</source>
     <destination>/mnt/path/target_data file_mountpoint</destination>
</mountpoint>
```

3. Optional: If you have a raw device on the source, you must specify the path for the raw device on the source, and then specify destination auto-generate=`"true`" for the destination.

   Unlike in the clone mapping file from previous versions of SnapManager for Oracle, you cannot specify a location for the raw device on the destination. SnapManager for Oracle will choose the next available device name for the cloned raw device.

   The following example displays the raw device syntax that you use in clone specification:

```
<raw-device>
     <source>/dev/raw/raw1</source>
     <destination auto-generate="true"/>
</raw-device>
```

4. In the database specification component, identify the control file information as a list of the control files that you want created for the clone.

   The database specification specifies the database options for the clone such as control files, redo logs, archive logs, and Oracle parameters.

   The following example displays the control file syntax that you use in clone specification:

```
<controlfiles>
     <file>/mnt/path/clonename/control/control01.ctl</file>
     <file>/mnt/path/clonename/control/control02.ctl</file>
</controlfiles>
```

5. Specify the redo log structure for the clone.

   The following example displays the redo log directory structure for cloning:

```
<redologs>
     <redogroup>
          <file>/mnt/path/clonename/redo/redo01.log</file>
          <number>1</number>
          <size unit="M">100</size>
     </redogroup>
     <redogroup>
         <file>/mnt/path/clonename/redo/redo02.log</file>
         <number>2</number>
         <size unit="M">100</size>
     </redogroup>
</redologs>
```

6. Specify the Oracle parameters that should be set to different values in the cloned database. If you are using Oracle 10, you must specify the following parameters:

- Background dump
- Core dump
- User dump
- (Optional) Archive logs

> If the parameter values are not set correctly, the clone operation is stopped and you receive an error message.

If you do not specify the location where archive logs are stored, SnapManager creates the clone in noarchivelog mode. SnapManager copies this parameter information into the init.ora file of the clone.

+ The following example displays the parameter syntax that you use in clone specification:

+

```
<parameters>
     <parameter>
          <name>log_archive_dest_1</name>
          <value>LOCATION=/mnt/path/clonename/archive</value>
     </parameter>
</parameters>
```

+ You can use a default value by using a default element within the parameter element. In the following example, the os_authentication_prefix parameter will take the default value because the default element is specified:

+

```
<parameters>
     <parameter>
          <name>os_authent_prefix</name>
          <default></default>
     </parameter>
</parameters>
```

+ You can specify an empty string as the value for a parameter by using an empty element. In the following example, the os_authentication_prefix will be set to an empty string:

+

```
<parameters>
     <parameter>
          <name>os_authent_prefix</name>
          <value></value>
     </parameter>
</parameters>
```

+ NOTE: You can use the value from the source database's init.ora file for the parameter by not specifying any element.

+ If a parameter has multiple values, then you can provide the parameter values separated by commas. For example, if you want to move the data files from one location to another, then you can use the db_file_name_convert parameter and specify the data file paths separated by commas as seen in the following example:

+

```
<parameters>
     <parameter>
          <name>db_file_name_convert</name>
          <value>>/mnt/path/clonename/data
file1,/mnt/path/clonename/data file2</value>
     </parameter>
</parameters>
```

+ If you want to move the log files from one location to another, then following you can use the log_file_name_convert parameter and specify the log file paths separated by commas, as seen in the example:

+

```
<parameters>
     <parameter>
          <name>log_file_name_convert</name>

<value>>/mnt/path/clonename/archivle1,/mnt/path/clonename/archivle2</val
ue>
     </parameter>
</parameters>
```

7. Optional: Specify arbitrary SQL statements to execute against the clone when it is online.

   You can use the SQL statements to perform tasks such as re-creating the temp files in the cloned database.

You must ensure that a semicolon is not included at the end of the SQL statement.

The following is a sample SQL statement that you execute as part of the clone operation:

```
<sql-statements>
   <sql-statement>
     ALTER TABLESPACE TEMP ADD
     TEMPFILE '/mnt/path/clonename/temp_user01.dbf'
     SIZE 41943040 REUSE AUTOEXTEND ON NEXT 655360
     MAXSIZE 32767M
   </sql-statement>
</sql-statements>
```

Clone specification example

The following example displays the clone specification structure, including both the storage and database specification components:

```
<clone-specification xmlns="http://www.example.com>

   <storage-specification>
     <storage-mapping>
        <mountpoint>
          <source>/mnt/path/source_mountpoint</source>
          <destination>/mnt/path/target_mountpoint</destination>
        </mountpoint>
        <raw-device>
          <source>/dev/raw/raw1</source>
          <destination auto-generate="true"/>
        </raw-device>
        <raw-device>
          <source>/dev/raw/raw2</source>
          <destination auto-generate="true"/>
        </raw-device>
     </storage-mapping>
   </storage-specification>

   <database-specification>
     <controlfiles>
       <file>/mnt/path/clonename/control/control01.ctl</file>
       <file>/mnt/path/clonename/control/control02.ctl</file>
     </controlfiles>
     <redologs>
         <redogroup>
```

```
            <file>/mnt/path/clonename/redo/redo01.log</file>
            <number>1</number>
            <size unit="M">100</size>
        </redogroup>
        <redogroup>
            <file>/mnt/path/clonename/redo/redo02.log</file>
            <number>2</number>
            <size unit="M">100</size>
        </redogroup>
    </redologs>
    <parameters>
      <parameter>
        <name>log_archive_dest_1</name>
        <value>LOCATION=/mnt/path/clonename/archive</value>
      </parameter>
      <parameter>
        <name>background_dump_dest</name>
        <value>/mnt/path/clonename/admin/bdump</value>
      </parameter>
      <parameter>
        <name>core_dump_dest</name>
        <value>/mnt/path/clonename/admin/cdump</value>
      </parameter>
      <parameter>
        <name>user_dump_dest</name>
        <value>/mnt/path/clonename/admin/udump</value>
      </parameter>
    </parameters>
   </database-specification>
</clone-specification>
```

Related information

Cloning databases and using custom plug-in scripts

Cloning databases from backups

Cloning databases in the current state

Considerations for cloning a database to an alternate host

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.