Setting role-based access control capabilities and roles

SnapManager Oracle

Aksel Davis
February 05, 2021

This PDF was generated from https://docs.netapp.com/us-en/snapmanager-oracle/unix-administration/task_setting_role-based_access_control_capabilities_and_roles.html on August 06, 2021.
Always check docs.netapp.com for the latest.

Table of Contents

Setting role-based access control capabilities and roles 1

Setting role-based access control capabilities and roles

After you enable role-based access control (RBAC) for SnapManager using SnapDrive, you can add RBAC capabilities and users to roles to perform SnapManager operations.

You must create a group in the Data Fabric Manager server and add the group to both primary and secondary storage systems. Run the following commands:

- dfm group create smo_grp
- dfm group add smo_grpprimary_storage_system
- dfm group add smo_grpsecondary_storage_system

You can use either the Operations Manager web interface or the Data Fabric Manager server command-line interface (CLI) to modify RBAC capabilities and roles.

The table lists the RBAC capabilities required to perform SnapManager operations:

SnapManager operations	RBAC capabilities required when data protection is not enabled	RBAC capabilities required when data protection is enabled
Profile create or profile update	SD.Storage.Read (smo_grp)	SD.Storage.Read (SMO_profile dataset)
Profile protection	DFM.Database.Write (smo_grp) SD.Storage.Read (smo_grp) SD.Config.Read (smo_grp) SD.Config.Write (smo_grp) SD.Config.Delete (smo_grp) GlobalDataProtection	None
Backup create	SD.Storage.Read (smo_grp) SD.Snapshot.Write (smo_grp) SD.Snapshot.Read (smo_grp) SD.Snapshot.Delete (smo_grp)	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Write (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.Snapshot.Delete (SMO_profile dataset)

SnapManager operations	RBAC capabilities required when data protection is not enabled	RBAC capabilities required when data protection is enabled
Backup create (with DBverify)	SD.Storage.Read (smo_grp) SD.Snapshot.Write (smo_grp) SD.Snapshot.Read (smo_grp) SD.Snapshot.Delete (smo_grp) SD.SnapShot.Clone (smo_grp)	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Write (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.Snapshot.Delete (SMO_profile dataset) SD.SnapShot.Clone (SMO_profile dataset)
Backup create (with RMAN)	SD.Storage.Read (smo_grp) SD.Snapshot.Write (smo_grp) SD.Snapshot.Read (smo_grp) SD.Snapshot.Delete (smo_grp) SD.SnapShot.Clone (smo_grp)	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Write (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.Snapshot.Delete (SMO_profile dataset) SD.SnapShot.Clone (SMO_profile dataset)
Backup restore	SD.Storage.Read (smo_grp) SD.Snapshot.Write (smo_grp) SD.Snapshot.Read (smo_grp) SD.Snapshot.Delete (smo_grp) SD.SnapShot.Clone (smo_grp) SD.Snapshot.Restore (smo_grp)	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Write (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.Snapshot.Delete (SMO_profile dataset) SD.SnapShot.Clone (SMO_profile dataset) SD.Snapshot.Restore (SMO_profile dataset)
Backup delete	SD.Snapshot.Delete (smo_grp)	SD.Snapshot.Delete (SMO_profile dataset)

SnapManager operations	RBAC capabilities required when data protection is not enabled	RBAC capabilities required when data protection is enabled
Backup verify	SD.Storage.Read (smo_grp) SD.Snapshot.Read (smo_grp) SD.Snapshot.Clone (smo_grp))	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.Snapshot.Clone (SMO_profile dataset)
Backup mount	SD.Storage.Read (smo_grp) SD.Snapshot.Read (smo_grp) SD.Snapshot.Clone (smo_grp)	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.Snapshot.Clone (SMO_profile dataset)
Backup unmount	SD.Snapshot.Clone (smo_grp)	SD.Snapshot.Clone (SMO_profile dataset)
Clone create	SD.Storage.Read (smo_grp) SD.Snapshot.Read (smo_grp) SD.SnapShot.Clone (smo_grp)	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.SnapShot.Clone (SMO_profile dataset)
Clone delete	SD.Snapshot.Clone (smo_grp)	SD.Snapshot.Clone (SMO_profile dataset)
Clone split	SD.Storage.Read (smo_grp) SD.Snapshot.Read (smo_grp) SD.SnapShot.Clone (smo_grp) SD.Snapshot.Delete (smo_grp) SD.Storage.Write (smo_grp)	SD.Storage.Read (SMO_profile dataset) SD.Snapshot.Read (SMO_profile dataset) SD.SnapShot.Clone (SMO_profile dataset) SD.Snapshot.Delete (SMO_profile dataset) SD.Storage.Write (SMO_profile dataset)

For details about defining RBAC capabilities, see the *OnCommand Unified Manager Operations Manager*

Administration Guide.

1. Access the Operations Manager console.
2. From the Setup menu, select **Roles**.
3. Select an existing role or create a new one.
4. To assign operations to your database storage resources, click **Add capabilities**.
5. On the Edit Role Settings page, to save your changes to the role, click **Update**.

Related information

OnCommand Unified Manager Operations Manager Administration Guide: mysupport.netapp.com/documentation/productsatoz/index.html

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.