DNS サーバを設定する

StorageGRID

NetApp
March 18, 2022

This PDF was generated from https://docs.netapp.com/ja-jp/storagegrid-116/maintain/modifying-dns-configuration-for-single-grid-node.html on March 18, 2022. Always check docs.netapp.com for the latest.

目次

DNS サーバを設定する 1
単一のグリッドノードの DNS 設定を変更します 1

DNS サーバを設定する

IP アドレスではなく Fully Qualified Domain Name （ FQDN ；完全修飾ドメイン名）ホスト名を使用できるよう、 Domain Name System （ DNS ；ドメインネームシステム）サーバを追加、削除、更新することができます。

必要なもの

- を使用して Grid Manager にサインインする必要があります サポートされている Web ブラウザ。
- Maintenance または Root Access 権限が必要です。
- 設定する DNS サーバの IP アドレスを確認しておく必要があります。

DNS サーバ情報を指定すると、 E メール通知や SNMP 通知、および AutoSupport に、 IP アドレスではなく完全修飾ドメイン名（ FQDN ）ホスト名を使用できるようになります。DNS サーバは少なくとも 2 つ指定することを推奨します。

> DNS サーバの IP アドレスは 2~6 つ指定します。一般に、ネットワーク分離が発生した場合に各サイトがローカルにアクセスできる DNS サーバを選択します。これにより、分離されたサイトは引き続き DNS サービスにアクセスできます。グリッド全体の DNS サーバリストを設定したら、次の操作を実行できます 各ノードの DNS サーバリストをさらにカスタマイズします。

DNS サーバ情報を省略したり誤って設定したりすると、各グリッドノードの SSM サービスで DNST アラームがトリガーされます。このアラームは、 DNS が正しく設定され、新しいサーバ情報がすべてのグリッドノードに配信された時点で解除されます。

手順

1. [* maintenance * （メンテナンス * ）] > [* Network * （ネットワーク * ）] > [* DNS servers * （ * DNS サーバー
2. 必要に応じて、 Servers セクションで、アップデートを追加するか、 DNS サーバエントリを削除します。

   サイトごとに少なくとも 2 つの DNS サーバを指定することを推奨します。DNS サーバは 6 つまで指定できます。

3. [保存（ Save ）] をクリックします。

単一のグリッドノードの DNS 設定を変更します

環境全体でグローバルにドメインネームシステム（ DNS ）を設定する代わりに、スクリプトを実行してグリッドノードごとに DNS を設定することができます。

一般に、 Grid Manager で * maintenance * > * Network * > * DNS servers * オプションを使用して DNS サーバを設定します。次のスクリプトは、グリッドノードごとに異なる DNS サーバを使用する必要がある場合にのみ使用します。

1. プライマリ管理ノードにログインします。
   a. 次のコマンドを入力します。 ssh admin@*primary_Admin_Node_IP*`

b. 「 passwords.txt 」ファイルに記載されたパスワードを入力します。
c. root に切り替えるには、次のコマンドを入力します
d. 「 passwords.txt 」ファイルに記載されたパスワードを入力します。

   root としてログインすると、プロンプトは「 $` 」から「 #」 に変わります。

e. SSH エージェントに SSH 秘密鍵を追加します。「 ssh-add 」と入力します
f. 「 passwords.txt 」ファイルに記載された SSH アクセスパスワードを入力します。

2. [[log_in_on_node] カスタム DNS 設定で更新するノードにログインします：「 ssh_node_name
3. DNS セットアップ・スクリプトを実行します： 'setup_resolv.RB.

   スクリプトから、サポートされるコマンドの一覧が返されます。

```
Tool to modify external name servers

available commands:
  add search <domain>
               add a specified domain to search list
               e.g.> add search netapp.com
  remove search <domain>
               remove a specified domain from list
               e.g.> remove search netapp.com
  add nameserver <ip>
               add a specified IP address to the name server list
               e.g.> add nameserver 192.0.2.65
  remove nameserver <ip>
               remove a specified IP address from list
               e.g.> remove nameserver 192.0.2.65
  remove nameserver all
               remove all nameservers from list
  save         write configuration to disk and quit
  abort        quit without saving changes
  help         display this help message


Current list of name servers:
    192.0.2.64
Name servers inherited from global DNS configuration:
    192.0.2.126
    192.0.2.127
Current list of search entries:
    netapp.com

Enter command [`add search <domain>|remove search <domain>|add
nameserver <ip>`]
               [`remove nameserver <ip>|remove nameserver
all|save|abort|help`]
```

4. ネットワークにドメインネームサービスを提供するサーバの IPv4 アドレスを追加します。「 add <nameserver ip_address > 」
5. ネームサーバを追加するには 'add nameserver' コマンドを繰り返します
6. 他のコマンドについてはプロンプトが表示されたら、その指示に従います。
7. 変更内容を保存してアプリケーションを終了します :'save
8. サーバ上のコマンドシェルを閉じます :`exit
9. グリッドノードごとに、からの手順を繰り返します ノードにログインします から コマンドシェルを閉じています。

10. 他のサーバにパスワードなしでアクセスする必要がなくなった場合は、 SSH エージェントから秘密鍵を削除します。「 ssh-add-d` 」と入力します

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.